



PUBLIC

# Radio Frequency

## DOCUMENT HISTORY

Document Version	Description
3.0	Revised 2023-02-17
2.5	Guide now also relevant for EWM in SAP S/4HANA
2.4	Updated template 2022-04-15
2.3	Revised 2016-05-02
2.2	Revised 2008-03-14
2.1	Revised 2006-10-26
2.0	Update after workshop 2004-05-07
1.2	Update 2004-01-27
1.1	Update 2003-11-17
1.0	First official release of this guide

# Contents

1	OBJECTIVE .....	6
1.1	Architecture Description of the RF Framework.....	6
1.2	RF Runtime – Framework Interaction Model .....	6
1.3	RF Framework Customizing Overview .....	7
1.4	Send Messages to Working Resources .....	9
2	RF FRAMEWORK.....	11
2.1	Structure.....	11
2.2	Important Tables and Structures .....	11
2.3	Important Classes.....	12
2.4	Debugging.....	12
2.4.1	Breakpoints .....	12
2.4.2	Breakpoint IDs .....	13
3	RF COOKBOOK .....	13
3.1	Define the Application.....	13
3.2	Define Presentation Profiles.....	13
3.3	Define Display Profiles.....	13
3.3.1	Template Screens .....	14
3.3.2	Message Handling.....	14
3.4	Define Personalization Profile .....	15
3.5	Define Logical Transaction.....	15
3.6	Assign Text to Logical Transaction and Other Objects .....	16
3.7	Create Menu Item.....	16
3.8	Assign Text to Menu Item .....	16
3.9	Create Menu Hierarchy Including Submenus and Transactions.....	16
3.10	Define Logical Transaction Steps .....	16
3.11	Define Initial Step for Logical Transaction.....	17
3.12	Define Application Data Containers .....	17
3.12.1	Using Tables in the RF Framework.....	18
3.13	Create Template Screen .....	18
3.13.1	Use Custom Template Dynpro .....	18
3.14	Create Sub-Screens .....	18
3.14.1	Predefined Screen Groups .....	19
3.14.2	Automatic Page Up / Page Down Implementation.....	20
3.14.3	Field to Field Navigation.....	20
3.14.4	Exit a Screen Without Saving Data in Internal Structures.....	21
3.14.5	Exit a Screen and Save Data in Internal Structures .....	21
3.14.6	Exit a Screen and Call the Content Provider .....	21
3.15	Define Function Code Catalog.....	21
3.15.1	Predefined Function Codes in the RF Framework.....	21
3.16	Assign Text to Function Code .....	22
3.17	Create Services to Support Business Logic .....	22

3.18	Define State Catalogue.....	23
3.19	Map Logical Transaction Step to Sub-Screen.....	23
3.20	Define Function Code Profile .....	23
3.20.1	GUI Status Is Defined for the Template .....	24
3.20.2	Connect Screen Function Codes and RF Framework Function Codes.....	24
3.20.3	Handle More Function Codes Than Available Buttons on a Screen or Step.....	25
3.20.4	Add Standard Function Codes as Buttons.....	26
3.20.5	Switch Off Function Codes Not Supported in SAP S/4HANA Cloud.....	27
3.20.6	Switch Off Fields Not Supported in SAP S/4HANA Cloud.....	27
3.21	Define Step Flow .....	27
3.21.1	PBO of Initial Screen After Menu Selection .....	27
3.21.2	PAI of Screen and Direct Display of Next Screen.....	28
3.21.3	PAI of Screen and PBO of Next Screen .....	28
3.21.4	Call of Common Screen from Several Screens During Transaction .....	28
3.21.5	Customizable ENTER / Set Next Step Dynamically Using the CP .....	28
3.21.6	Additional Information .....	29
3.22	Set Default Navigation at Transaction End.....	30
3.23	Set Verification Profile .....	30
3.23.1	Verification.....	30
3.24	Presentation Device Catalog .....	31
4	LAYOUT .....	32
4.1	Screen.....	32
4.2	Fields.....	32
4.2.1	Field Length .....	32
5	PROGRAMMING INFORMATION .....	33
5.1	Posting.....	33
5.2	Exception Handling and Using Shortcuts .....	33
5.2.1	Navigation.....	33
5.2.2	Exceptions.....	34
5.3	Differences.....	34
5.4	Support LIST Functions.....	34
5.5	Display of Text (from Delivery or Hazardous Material) .....	34
5.6	Methods Available to the Content Provider.....	34
5.6.1	Methods into the Framework .....	34
5.6.2	Methods out of the Framework .....	35
5.7	Global Variables .....	35
5.8	Display Technical Data on GUI Title of RF UI.....	36
5.9	Hard-Coded Logical Transaction.....	37
5.10	BADIs Used to Enhance RF Framework Customizing.....	38
6	USING THE TOOLS PROVIDED.....	39
6.1	Menu Manager .....	39
6.2	Screen Manager.....	40
6.2.1	Create, Copy, and Delete Display Profiles.....	40

6.2.2	Edit Screens of a Display Profile .....	42
6.3	Wizards .....	43
6.3.1	Split Screen .....	43
6.3.2	Modify Screen.....	43
6.3.3	Error Message Handling in RF Wizard.....	43
6.4	RF Log .....	43
6.4.1	Activation.....	44
6.4.3	Monitoring .....	45
6.4.4	Reference Objects .....	45
7	SAP GUI for HTML .....	46
7.1	Design Mode.....	47

# 1 OBJECTIVE


Note: The information contained in this how-to guide applies to both SAP EWM and EWM in SAP S/4HANA.

SAP has developed a radio frequency (RF) concept.

This RF cookbook helps developers to begin working in the RF framework. It answers frequently asked questions and helps to avoid common errors. This RF cookbook also provides some useful tips about the standard layout and screen structure that should be applied in the standard transactions.

Initially, the RF framework will be used in Extended Warehouse Management (EWM). However, the RF framework is application-independent and could also be used in other projects or applications.

## 1.1 Architecture Description of the RF Framework



Transaction /SCWM/RFUI is the starting point for all logical RF transactions in EWM. Logical transactions cannot be started directly from the SAP Easy Access screen and no equivalent transaction has been created in SE93.

The Easy Enhancement Workbench (EEWB), which can be used for customer enhancements, is integrated into the RF framework. Within the EEWB, users execute an RF process and when the modification screen is reached, the enhancement tool is triggered. Users then select the type of enhancement that they want to carry out. The appropriate enhancement wizard launches and guides the user through the enhancement process. If the user wants to enhance fields on the user interface, the screen painter is called once the enhancement is complete so that further adjustments to the screen can be made manually. This is part of post processing.

## 1.2 RF Runtime – Framework Interaction Model

The RF framework architecture consists of three distinct layers:


1. Dynpro layer
2. Business logic layer
3. Content provider

The dynpro layer is concerned with all screen-related data, display profiles, presentation devices, sub-screens, and templates.

At runtime, the business logic layer receives transactional parameters such as next step, screen, function code profile from the underlying Customizing settings.

Content provider stores and supplies the relevant data for processing.

The following sequence diagram shows how these layers interact.



### 1.3 RF Framework Customizing Overview

Customizing for the radio frequency (RF) framework comprises the following areas:

1. User and resource settings
2. Interface parameters and communication structures
3. Basic building blocks
4. Configuration and scenario assignments

In Customizing (transaction `SPRO`), the main Customizing activities for the radio frequency framework are available under *Extended Warehouse Management* ⑦ *Mobile Data Entry*.

▼	Extended Warehouse Management	
▷	Master Data	
▷	Goods Receipt Process	
▷	Goods Issue Process	
▷	Internal Warehouse Processes	
▷	Cross-Process Settings	
▷	Materialflusssystem (MFS)	
▷	Arbeitsmanagement	
▷	Monitoring	
▷	Interfaces	
▼	Mobile Data Entry	
▼	Radio Frequency (RF) Framework	
	Define Steps in Logical Transactions	
	RF Menu Manager	
	RF Screen Manager	
	Assign Presentation Profile to Warehouse	
▼	Verification Control	
	Define Warehouse-Specific Verification	
	Define Warehouse-Specific Verification Determination	
	Maintain Bar Code Specification	
	Assign Fkeys to Standard Functions	
▷	Business Add-Ins (BAdIs) for Extended Warehouse Management	

The Customizing activity *Define Steps in Logical Transaction* contains the following submenus:

	Define Application Parameters
▼	Define Presentation Profiles
	Define Personalization Profiles
▼	Define Steps
	Define States
▼	Define Function codes
	Define Function code text
	Define Validation Objects
▼	Define Logical Transactions
	Define Presentation texts
	Define Logical Transaction step flow
	Define Inter-Transaction flow
	Define Validation Profile
	Define Function code Profile
	Map Logical Transaction Step to Sub-Screen

**User and resource settings** support the definition of new presentation and personalization profiles, which are required to define behavior that varies from standard configuration. These profiles are linked to resource logons, making it possible to define alternative responses (such as displaying a user-defined screen instead of the standard screen) for a particular user or user group.

**Interface parameters and communication structures** can be defined for data communication between different screens (dynpros). For more information, see the *Define Application Parameters* option.

**Basic building blocks** include the definitions of logical transactions, steps, and function codes.

**Configuration** includes assigning steps to logical transactions and their flow, determining screens, assigning



function codes, and assigning validations. For more information, see the following sections.


You can call some Customizing activities directly using transaction codes, for example, /SCWM/RFMENU for the RF Menu Manager or /SCWM/RFSCR for the RF Screen Manager.

You can call Presentation Device Maintenance using transaction /SCWM/PRDVC.

## 1.4 Send Messages to Working Resources

You can send messages to different resources from the warehouse management monitor. To do so, proceed as follows:

1. Call transaction /SCWM/MON.



2. Enter the warehouse number and the variant of the monitor.
3. Expand the *Resource Management* node and double-click *Resource*.



4. Enter one or more resource names on the selection screen. The resources are displayed on the right side.

Resource	Rsrcr Type	Rsrcr Grp	DefPresDvc	User	RF Exec. Q	Actual Queue	Stor. Type	Logon Date	Time
GELLERTI	RT01	BUD	PRES	GELLERTI	X	OUTBOUND		29.12.2009	21:03:48
SZALAIA	RTAS	RGAS	PRES	SZALAIA	X	INTERNAL	0050	02.12.2009	16:47:27
VALOVICS	RTAS	RGAS	PRES						00:00:00
KERTESID	RT01	RGAS	PRES						00:00:00
RADMANN	RTAS	RGAS	PRES						00:00:00

5. Select the relevant resource names and choose *More Methods* to send messages to the selected resources.

Resource									
Send Message									
Resource	Maint. Resource	resDvc	User	RF Exec.	Q	Actual Queue	Stor. Type	Logon Date	Time
GELLERT	Logon Resource	S	GELLERT	X		OUTBOUND		29.12.2009	21:03:48
SZALAIA	Logoff Resource	S	SZALAIA	X		INTERNAL	0050	02.12.2009	16:47:27
VALOVICS	Change Queue	S							00:00:00
KERTESI	Change ResGrp	S							00:00:00
RADMANN		S							00:00:00

6. Enter the message text in the dialog box and choose *Send Message*. If the resource is logged on to the RF application, the message is displayed.

### SAP Radio-Frequency

VALOVICS / 31.12.09 / 11:04:18 / Please  
return to your parking place.

Enter


You can deactivate the function for sending and processing RF resource messages by calling transaction /SCWM/ RSCMSG\_DEACT. Alternatively, choose the following on the SAP Easy Access screen:

SAP menu:

- ▷ Office
- ▷ Cross-Application Components
- ▼ Extended Warehouse Management
  - ▷ Monitoring
  - ▷ Delivery Processing
  - ▷ Work Scheduling
  - ▷ Execution
  - ▷ Shipping and Receiving
  - ▷ Physical Inventory
  - ▷ Labor Management
  - ▼ Master Data
    - ▢ /SCMB/SCUMAIN - Maintain Supply Chain Unit
    - ▢ BP - Maintain Business Partner
    - ▢ /SCWM/PRDVC - Maintain Presentation Devices
    - ▢ /SCWM/DSGR - Maintain Consolidation Group
    - ▢ /SCWM/73000001 - Assign Storage Bins for VAS Consumption Posting
    - ▷ Classification System
    - ▼ Resource Management
      - ▢ /SCWM/RGRP - Maintain Resource Group
      - ▢ /SCWM/QSEQ - Maintain Queue Sequence for Resource Group
      - ▢ /SCWM/RSRC - Maintain Resource
      - ▢ /SCWM/EXECPR - Maintain Execution Priorities
      - ▢ /SCWM/USER - Maintain Users
      - ▢ /SCWM/REC\_ACTIVATE - Activate Resource Execution Control for Storage Groups
      - ▢ /SCWM/QTSQ - Maintain Queue Type Sequence
      - ▢ /SCWM/RSCMSG\_DEACT - Deactivate Messages to Resources
      - ▷ Processor

Activate or deactivate the function for sending messages to resources at warehouse level by selecting or clearing the checkbox in the *Deactivate* column.

By default, messages can be sent, meaning that the checkbox is not selected.



Note:

1. If you deactivate the function for sending messages for the warehouse, you cannot send messages to the resource in the monitor. The message receipt process is also deactivated in the RF framework. If you attempt to send a message to the resource in the monitor, the system displays an error message.
2. When you change the *Deactivate* field in the Customizing settings, you must restart the monitor and log in again for the change to be applied to the resource.

## 2 RF FRAMEWORK

### 2.1 Structure

The RF framework is developed in package /SCWM/RF\_FRAMEWORK.

### 2.2 Important Tables and Structures

Table	Description
/SCWM/TAPPL_CAT	Application, for example, WME
/SCWM/TDPRF_CAT	Display profile
/SCWM/TFCOD_CAT	Function code catalog
/SCWM/TFCOD_PRF	Function code profile
/SCWM/TMENU_CAT	Menu catalog
/SCWM/TMENU_HIER	Menu hierarchy
/SCWM/TOBJ_TXT	Object text
/SCWM/TPARAM_CAT	Data container
/SCWM/TPRDV_CAT	Presentation device
/SCWM/TPRES_CAT	Presentation profile
/SCWM/TPRSN_PRF	Personalization profile

/SCWM/TSTAT_CAT	State catalog
/SCWM/TSTEP_CAT	Steps
/SCWM/TSTEP_FLOW	Step flow
/SCWM/TSTEP_SCR	Mapping of foreground steps to sub-screen
/SCWM/TTRNS_CAT	Logical transactions
/SCWM/TTRNS_NAV	Navigation at end of logical transaction
/SCWM/TVALID_PRF	Verification and validation profile
/SCWM/TVLID_CAT	Verification and validation objects

## 2.3 Important Classes

Class	Description
/SCWM/CL_RF_BLL_DB	Presentation data access
/SCWM/CL_RF_BLL_SRVC	RF Business Logic Layer
/SCWM/CL_RF_DYNPRO_DB	Dynpro Layer Data Access
/SCWM/CL_RF_DYNPRO_SRVC	Dynpro Layer Services

## 2.4 Debugging

### 2.4.1 Breakpoints

#### 2.4.1.1 Method /SCWM/CL\_RF\_BLL\_SRVC=>CALL\_FLOW\_PROCESS

This method calls the function modules defined in /SCWM/TSTEP\_FLOW.

#### 2.4.1.2 Method /SCWM/CL\_RF\_BLL\_SRVC=>GET\_STEP\_FLOW

This method reads table /SCWM/TSTEP\_FLOW with the actual step data to determine the next step.

#### 2.4.1.3 Method /SCWM/CL\_RF\_BLL\_SRVC=>RUN

This method is called using transaction /SCWM/RFUI. It contains the loop in which the steps and screens are called or processed.

#### 2.4.1.4 Method /SCWM/CL\_RF\_BLL\_SRVC=>DISPLAY\_STEP

This method calls the screens once the verification field check has been called.

#### 2.4.1.5 Method /SCWM/CL\_RF\_BLL\_SRVC=>CHECK\_VERIF\_PRF

This method checks the verification fields that have been completed against the corresponding data fields. If a barcode function module is set in the verification profile (/SCWM/TVALID\_PRF field FMODUL\_TRNSL), this function module is called. If a verification function module is set in the verification profile (/SCWM/TVALID\_PRF field FMODUL\_VERIF), this function module is called. For more information about the verification process, see Verification.

### 2.4.2 Breakpoint IDs

In the RF framework, we have implemented the following breakpoint IDs:

- /SCWM/RF\_FRAMEWORK
- /SCWM/RF\_FRAME\_STEP
- /SCWM/RF\_FRAME\_VERIF

You can activate the breakpoint IDs in transaction SAAB.

## 3 RF COOKBOOK

### 3.1 Define the Application

An application is the highest organizational level in the radio frequency (RF) framework. At application level, you define the start transaction. In the standard SAP system, the start transaction is /SCWM/RFUI.

The application for Extended Warehouse Management (EWM) is 01.

In addition, you can define a function module to control the verification fields from an application-relevant point of view. This means that all verification fields in an RF transaction are ready for input. This function module enables you to deactivate verification fields in a process-specific manner. The function module used for EWM is /SCWM/RF\_WME\_SET\_VERIFICATION.

To maintain application data, call transaction SM30 and enter view /SCWM/V\_TAPPL\_CAT (for more information, see SAP Note 938314). The data is stored in table /SCWM/TAPPL\_CAT.

### 3.2 Define Presentation Profiles

The presentation profile (together with the personalization profile) is used to support different menu structures for different users. The presentation profile is assigned to the application.

The presentation profile for the standard transaction is \*\*\*\*.

You can maintain the presentation profile by choosing *Define Presentation Profiles*. The records are stored in table /SCWM/TPRES\_CAT.

### 3.3 Define Display Profiles

The display profile is used to support different devices and their different screen characteristics. We provide the following display profiles for standard RF transactions:

- Display profile \*\* for screens in landscape mode
- Display profile \*2 for screens in portrait mode
- Display profile \*1 for voice-enabled dynpros

For the display profile, you specify the height and width of your total screen (landscape mode 8x40 or portrait mode 15x26). You also specify the template program (/SCWM/SAPLRF\_TMPL) and screens (landscape mode 0001 and 0002 for messages or portrait mode 0021 and 0022 for messages). You also define the following at profile level:

- Button length (8)
- Number of buttons (4)
- Length of menu items (20)
- How error messages are displayed (0 = display on a separate screen)
- Where error messages are displayed

You can use the parameters BEEP\_INFO, BEEP\_WARN, and BEEP\_ERR to maintain the number of beeps processed by the device when a message is displayed. This works only if the device supports the beep function. See chapter 3.24 Presentation Device Catalog for more information about sound support.

You can create a display profile record in the RF screen manager (transaction /SCWM/RFSCR) or in the Customizing activity *RF Screen Manager* in Customizing for *Extended Warehouse Management* under *Mobile Data Entry > Radio Frequency (RF) Framework*. The data is stored in table /SCWM/TDPRF\_CAT.



As there are several standard profiles, you can use the RF screen manager to assign a customer-specific display profile to a standard profile. This is needed if the customer-specific display profile doesn't contain all dynpros. In this case, the RF framework takes the missing dynpros from the standard profile. For example, you create display profile Z1. This display profile doesn't contain all relevant dynpros. In the RF screen manager, you defined the standard profile for Z1 as \*2. If the RF framework doesn't find a dynpro in Z1, it takes the one from \*2.

The display profile is an attribute of the presentation device that is entered at the RF logon step. By default, display profile '\*\*' is taken. The RF framework tries to determine the screen orientation to display the RF logon screen in the right screen orientation (RF logon screen of display profile \*2 for RF devices with portrait screen orientation). This happens in method `/SCWM/CL_RF_BLL_SRVC-SET_PRDVC` by using function module `WEBGUI_GET_MOBILEDEVICE_INFO`.

In EWM, the dynpro in landscape mode and portrait mode share the same dynpro number but are located in different function groups. For example, RF picking dynpros in landscape mode are stored in function group `/SCWM/RF_PICKING`, the corresponding dynpros in portrait mode are stored in function group `/SCWM/RF_PICKING_PM`.

### 3.3.1 Template Screens

The standard SAP system is shipped with two templates, one for processing data and one for message handling. Both templates are sizes 8x40 (landscape) and 15x26 (portrait) and contain 7 or 13 lines for the sub-screen.

Landscape:

Dynpro 0001 with one line (last line) for four buttons and an input field for keyless navigation and exceptions.

Dynpro 0002 with only the message field on the last line (used only for message processing). The corresponding function group is `/SCWM/RF_TMPL`.

Portrait:

Dynpro 0021 with two buttons on the top line and two buttons and an input field for keyless navigation and exceptions on the last line.

Dynpro 0022 with only the message field on the last line (used only for message processing). The corresponding function group is `/SCWM/RF_TMPL`.

#### 3.3.1.1 Template Screen Title

No GUI title is shipped for SCM 5.0 or SCM 5.1. The title *SAP* appears on the RF screens. As of SCM 5.1, you can customize the GUI title for your template screens. The RF screen manager enables you to specify a function group and GUI title when you create a new display profile or copy an existing one. For existing display profiles, you can maintain view `/SCWM/V_DPRF_C` directly with transaction SM30.

If you set parameter ID `/SCWM/RF_TECH_TITLE`, you will see the logical transaction, step, dynpro program and dynpro number instead of 'SAP'.

In design mode in SAP S/4HANA, the logical transaction, step, dynpro program, and dynpro number are always shown. In SAP S/4HANA Cloud, the description of the RF transaction and the description of the step is shown because users of SAP S/4HANA Cloud don't have access to RF framework Customizing and make no use of the technical names.

### 3.3.2 Message Handling

Field `MSG_VIEW` in table `/SCWM/TDPRF_CAT` is used to control how the messages are processed.

An entry of 0 means that the message is displayed on a separate screen. This is screen 0002 in function group `/SCWM/RF_SSCR`.

An entry of 1 means that the message is displayed on the last line of the same screen or on the last line of the next screen. The template screen and the template program in which the message is processed must be specified in table `/SCWM/TDRPF_CAT`. In the standard SAP system, the template screen is 0002 in template program `/SCWM/SAPLRF_TMPL` (function group `/SCWM/RF_TMPL`).

If you want to use your own template dynpro, the message line field must refer to field `/SCWM/S_RF_SCRELM-MSGTX`.

The messages are defined at package level and assigned at function group level. As a result, there are two message classes. The standard message class in package /SCWM/CORE\_RF\_EN is /SCWM/RF\_EN and in package /SCWM/CORE\_RF\_DE it is /SCWM/RF\_DE.

If you display the messages on the bottom line, you can easily display the message on the separate screen using function code FULLMS. To do so, define a function key (with or without a corresponding button) and assign the function code FULLMS to it. If this function code is triggered, the actual message is displayed on message screen 0002. Function code FULLMS is always to be implemented, although it does not have to be shown in the toolbar. For more information about the function code and function code definitions, see Define Function Code Catalog.

The framework automatically retrieves all error messages of type E from the content provider's function modules. However, it may still be necessary to display messages while continuing with the coding in the function module and the step flow. In this case, you send a message with message type S or I. Note that this type of message cannot be retrieved due to the technical restrictions of the framework. In this case, you must use method /SCWM/CL\_RF\_BLL\_SRV=>MESSAGE. This method registers the message in the framework and the message is displayed when the screen next changes. You can also use method /SCWM/CL\_RF\_DYNPRO\_SERVICE=>DISPLAY\_MESSAGE.

Note that only one message can be displayed. If you send more messages, only the last message is displayed.

### 3.4 Define Personalization Profile

You use the personalization profile to empower customers to change the standard SAP system. Thanks to the personalization profile, you can support different user groups working in different menus and, therefore, different processes.

The personalization profile for standard transactions is \*\*.

You define the main menu entry for the personalization profile.

You can maintain the personalization profile in Customizing by choosing *Define Personalization Profile*. The data is stored in table /SCWM/TPRSN\_PRF.

### 3.5 Define Logical Transaction

A logical transaction encapsulates the processed action from beginning to end. It could involve screen changes and multiple postings including COMMIT WORK.

Logical transactions have no corresponding entries in transaction SE93 and can be called only from the RF menu or the RF logon step. A logical transaction can also be called using method /SCWM/CL\_RF\_BLL\_SRV=>START\_LTRANS (for example, from another logical transaction).

The authority check on object /SCWM/RFLT is also carried out in method /SCWM/CL\_RF\_BLL\_SRV=>START\_LTRANS.

For the logical transaction, you define an initial step (see below) or an SAP transaction. You can also define a step that is processed during recovery. The following naming convention for the first 2 characters should be considered:

Initials	Process
AH	Ad-hoc movements
IN	Inquiries
IV	Physical inventory
PA	Packing
PI	Picking
PT	Putaway
QM	Quality management

RF	RF framework
RS	Resource management
SH	Shipping and loading
SP	Spreading
UL	Unloading
WK	Independent of work process, for example, system-guided

Note that in the namespace for customers, there is also a hardcoded reserved namespace for industry-specific RF transactions. For more information, see include `/SCWM/LLMBPCF04`.

The reserved logical transaction is `RFMAIN`. This is the default logical transaction that is called when you start the RF framework with transaction `/SCWM/RFUI`. The initial step of `RFMAIN` is `MENU`.

Logical transactions are stored in table `/SCWM/TTRNS_CAT`.

### 3.6 Assign Text to Logical Transaction and Other Objects

For several objects, you can add texts for translation. These texts are stored *implicitly* using different Customizing settings for the RF framework.

Note that in the case of function codes, the function key (such as `F2`) is added automatically if you assign the function key to the function code in field `FNKEY` of table `/SCWM/TFCOD_PRF`. As a result, the remaining available space for the text is less than specified in `/SCWM/TDPRF_CAT`.

The length of the fields is defined in the display profile.

### 3.7 Create Menu Item

You can define your own menus in transaction `/SCWM/RFMENU`.

You create your menu items for the main menu and then for the submenus.

The menu items are stored in table `/SCWM/TMENU_CAT`.

### 3.8 Assign Text to Menu Item

You assign text to menu items in transaction `/SCWM/RFMENU`. In the case of menu items, the appropriate number is added and so it is not necessary to add the sequence number. The data is stored in table `/SCWM/TOBJ_TXT`. The length of the menu items is defined in the display profile.

### 3.9 Create Menu Hierarchy Including Submenus and Transactions

You create the menu hierarchy in transaction `/SCWM/RFMENU`.

Within the hierarchy, you define whether a logical transaction is triggered (field `LTRANS`) or whether the user jumps to a submenu (field `LMENU`).

We deliver a default menu that contains application 01, presentation profile `****`, and personalization profile `**`. These entries can be maintained only in an SAP system. In a customer system, these entries are locked for changes.

Note that the standard menu is maintained by a central team.

The menu hierarchy is stored in table `/SCWM/TMENU_HIER`.

### 3.10 Define Logical Transaction Steps

Any logical transaction consists of at least one step. If possible, steps defined for other logical transactions can be reused. Steps can be executed in the background or in the foreground. Each foreground step has a corresponding physical screen. Steps in the background can be combined.

The following naming convention for the first two characters must be considered:



Initials	Process
AH	Ad-hoc movements
IN	Inquiries
IV	Physical inventory
PA	Packing
PI	Picking
PT	Putaway
QM	Quality management
RF	RF framework
RS	Resource management
SH	Shipping and loading
SP	Spreading
UL	Unloading
WK	Independent of work process, for example, system-guided

Note that in the controlled namespace for customers, there is also a hardcoded reserved namespace for industry-specific RF transactions. For more information, see include `/SCWM/LLMBPCF04`.

Reserved steps are `RFLOGN`, `RFMENU`, `RFLIST`, and `RFMSG`. Steps are stored in table `/SCWM/TSTEP_CAT`.

### 3.11 Define Initial Step for Logical Transaction

The initial step is stored in the logical transaction data in the `ISTEP` field of table `/SCWM/TTRNS_CAT`.

### 3.12 Define Application Data Containers

Application data containers transmit data between the steps and from the program (content provider) to the screens. Data containers can be structures or tables. These structures or table types must be defined beforehand in the data dictionary.

The same data dictionary structure or table type can be defined only once within an application, for example, function modules, dynpro with structure, or dynpro with table.

Data containers are assigned to the corresponding structure or table in `/SCWM/TPARAM_CAT`. The maintenance menu in Customizing is *Define Application Parameters*.

Before you can use the data containers, you must inform the RF framework. The framework provides two methods: The first is to initialize the parameter previously used (`/SCWM/CL_RF_BLL_SRVC=>INIT_SCREEN_PARAM`) and the second is to register the parameter in the framework (`/SCWM/CL_RF_BLL_SRVC=>SET_SCREEN_PARAM`).

Registering the data container is mandatory. The best way to do so is to initialize the registration process on the PBO (process before output) screen and register all of the data containers that are used on the screen.

From a visual perspective, the RF framework acts as a library. Structures and tables defined in Customizing represent the books, and the data is stored within each of these books. In other words, the framework contains several types of data in "books". When the system displays a screen, the framework (library) provides only those structures and tables (books) that are required by the screen (reader). Even if the framework contains multiple data containers, only those that are actually needed are transferred to the screen or function module.

**Example:**

The framework contains several data containers: CS\_ADMIN, CS\_PTUY, CS\_UNLO, CS\_PACK, and so on.

The screen displays putaway data from CS\_PTUY only. In this case, the framework transfers CS\_PTUY to the screen and so the values of CS\_PTUY are displayed on the screen.

If CS\_PTUY is not defined as a data container or CS\_PTUY is not registered as a screen parameter, there is no data to transfer and so the screen will contain empty data.

### 3.12.1 Using Tables in the RF Framework

Function modules can use any number of tables. Each screen can present multiple structures but only one table. The content provider must specify which table will be presented by using method /SCWM/CL\_RF\_BLL\_SRVC=>SET\_SCR\_TABNAME. The content provider must also specify which line of the table will be presented by using method /SCWM/CL\_RF\_BLL\_SRVC=>SET\_LINE.

## 3.13 Create Template Screen

The template screen contains buttons and encompasses the sub-screen. It is an object that belongs to the RF framework, whereas the sub-screens belong to the content provider.

We provide a standard 8x40 template for devices with landscape screen orientation in program /SCWM/SAPLRF\_TMPL with screen 0001 for button handling and screen 0002 for message handling.

We provide a standard 15x26 template for devices with portrait screen orientation in program /SCWM/SAPLRF\_TMPL with screen 0021 for button handling and screen 0022 for message handling.

### 3.13.1 Use Custom Template Dynpro

If you want to make changes at template level, for example, placing a button, changing the number of buttons, or changing the size of the sub-screen, you must define your own template screen.

If you want to display an error message on the bottom line, the field must refer to /SCWM/S\_RF\_SCRELM-MSGTX.

## 3.14 Create Sub-Screens

Sub-screens belong to the content provider and should be developed in package /SCWM/CORE\_RF\_EN or /SCWM/CORE\_RF\_DE. The sub-screens must be stored in a function group. The naming convention for the function group is /SCWM/RF\_<Process> (for example, /SCWM/RF\_PUTAWAY or /SCWM/RF\_PICKING).

The flow logic (PBO and PAI) of the sub-screen must be simple. Furthermore, the two modules STATUS\_SSCR in PBO and USER\_COMMAND\_SSCR in PAI (process after input) are standard modules that must be included in the sub-screen. We recommend that you do not add your own modules to the sub-screen flow logic. All processing should be done in the function modules defined in step flow table

/SCWM/TSTEP\_FLOW. These two modules are also automatically added when you use the *Screen Management Tool* to change your standard screens.

The modules are part of include /SCWM/IRF\_SSCR. You must include this in the function pool of your function group.

The flow logic of a sub-screen should appear as follows:

PROCESS BEFORE OUTPUT.

```
* Common routine to control screen objects
*   before the dynpro is displayed.
* The module exists in include /SCWM/LRF_SSCRO01
  MODULE STATUS_SSCR.
*
```

PROCESS AFTER INPUT.

```
* Common routine to handle standard function codes
```

```
* The module exists in include /SCWM/LRF_SSCRI01
MODULE USER_COMMAND_SSCR.
```

The flow logic of a sub-screen with a step-loop should appear as follows:

```
PROCESS BEFORE OUTPUT.
* pass structures to the screen
* set screen attributes
MODULE status_sscr_loop.
* pass table rows to the step-loop
LOOP.
MODULE loop_output.
ENDLOOP.
* set (disable/enable) PGUP/PGDN pushbuttons on the screen
MODULE loop_scrolling_set.
*
PROCESS AFTER INPUT.
LOOP.
* save data of the step-loop elements
MODULE loop_input.
ENDLOOP.

* pass input to the application, return function code
* to the program
MODULE user_command_sscr.
```

All screen objects must be taken from the assigned structure of the appropriate data container. The screen objects must not have the same name as the container. You must use the structure of the table line for tables.

In the function pool definition you should add the include /SCWM/IRF\_SSCR, which contains the required subroutines and data definition.

Defining a button on the sub-screen is strictly forbidden because this could impact the ITS environment. Instead, use the button from the template screen (see Section 3.3.1).

### 3.14.1 Predefined Screen Groups

Screen groups 1 and 3 must only be used as described below. Your own coding should only use screen group 4.

#### 3.14.1.1 Group 1

001	Blocked for internal use to support required input fields. DO NOT USE this screen group. Group1 is filled/overwritten at runtime.
-----	---

#### 3.14.1.2 Group 3

001	Hide empty fields. If a verification field is assigned to a suppressed data field, the verification field will also be suppressed automatically without using screen groups.
-----	--

002	For verification fields only. Disable field after successful verification. This also marks the field as a verification field.
-----	---

### 3.14.2 Automatic Page Up / Page Down Implementation

Define a table type in the data dictionary.

Assign the table type to a parameter in table /SCWM/TPARAM\_CAT.

Use this table type in your function module in which you read the data and fill your parameter. Note that you must always define this in the CHANGING parameter.

Once you have filled the parameter data in your function module, call method SET\_SCR\_TABNAME from class /SCWM/CL\_RF\_BLL\_SRVC to register the table name in the RF framework and call method SET\_LINE from class /SCWM/CL\_RF\_BLL\_SRVC to register the first displayed line.

Note that the table name to be registered is the table type and not the parameter name.

Note also that the screen fields must be named in the same way as the line type of your table type in the dynpro.

The buttons on the dynpro must refer to /SCWM/S\_RF\_SCRELM-PGUP and /SCWM/S\_RF\_SCRELM-PGDN. We recommend that you implement the buttons with a length of 3 characters. The buttons must be defined with the function codes PGUP and PGDN.

The buttons are controlled by the RF framework.

#### \* Transfer table name into RF framework

```
CALL METHOD /scwm/cl_rf_bll_srvc=>set_scr_tabname
EXPORTING
    iv_scr_tabname = '/SCWM/TT_RF_PROTO_TAB'
```

#### \* Set displaying line number of table

```
CALL METHOD /scwm/cl_rf_bll_srvc=>set_line
EXPORTING
    iv_line = 1
```

You can use Page Up / Page Down to control either a screen or a step-loop on a screen. In the first case, your table contains multiple entries and only one entry is displayed on the screen at a time. With Page Down, the next entry in the table is displayed. In the second case, your screen contains a step-loop and you only control the behavior of the step-loop.

### 3.14.3 Field to Field Navigation

#### 3.14.3.1 Navigation Between Verification Fields

The cursor is always positioned in the first field that is ready for input. When a field is verified successfully, it is deactivated and the cursor is moved to the next field that is ready for input.

The content provider is not called during navigation. For more information, see *Verification*.

#### 3.14.3.2 Navigation Between Input Fields (No Verification Fields)

In contrast to the verification fields, normal input fields are not deactivated once data has been entered. As a result, navigation behavior differs.

The cursor is positioned in the first field that is ready for input. The current field is an attribute of the service class of the business logic layer (/SCWM/CL\_RF\_BLL\_SRVC). This class also provides two methods to get (GET\_FIELD) and set (SET\_FIELD) the current field. Navigation within the screen can be influenced using

these.

In the standard SAP system, the cursor is positioned in the next initial input field. Pay attention to any input fields that could contain a valid initial value. For example, an indicator with appropriate values of *blank* and *X*. In this case, you must mark all fields that have to be entered in the field attribute in the dynpro as *Input obligatory*.

You can also move the cursor manually using the `TAB` key or the arrow keys. The content provider is not called during navigation. The content provider is only called once all of the fields have been filled. If you want to process an error and position the cursor in a certain field, use method `/SCWM/CL_RF_BLL_SRVC=>SET_FIELD` for positioning.

### 3.14.3.3 Navigation on a Screen with Input Fields and Verification Fields

In this case, the navigation behavior processes the verification fields first and then the input fields.

## 3.14.4 Exit a Screen Without Saving Data in Internal Structures

If your screen contains input fields and you want to exit without saving the data in the internally used structures as defined in table `/SCWM/TPARAM_CAT`, you must do so by choosing *Back*. Otherwise, your data will be rendered inconsistent if you use the same data structures.

To enable this, assign the function code `BACK` in table `/SCWM/TFCOD_PRF` to a function key, button, or shortcut. In the step flow (table `/SCWM/TSTEP_FLOW`), an entry is not necessary because the content provider is not called.

## 3.14.5 Exit a Screen and Save Data in Internal Structures

In contrast to the `BACK` function code, `UPDBCK` updates the data on the stack and the screen called can use the updated data. With `UPDBCK`, the content provider is not called.

## 3.14.6 Exit a Screen and Call the Content Provider

In some cases, you have to call the content provider before you exit a screen. In this case, you cannot use `BACK` or `UPDBCK` directly. Assign another function code (such as `BACKF`) to your function key, button, or shortcut but use the key that is normally used for `BACK` (`F7`). With the new function code, the content provider is called and you can then set the `BACK` function code, which is processed by the framework. In this case, your step flow would be:

APPLIC	PRES_PRF	LTRANS	STEP	FCODE	FMODUL	SSTEP	PRMOD	FCODE_BCKG
01	****	LTX1	STEP2	BACKF	FM1	STEP2	1	BACK

Note that `PRMOD` must be 1, `SSTEP` = `STEP`, and `FCODE_BCKG` must be `BACK`.

## 3.15 Define Function Code Catalog

Define the required function codes of the buttons and function keys used in background step processing. To do so, choose the Customizing activity *Define Steps in Logical Transactions* and choose *Define Function Codes*. Do not define the function codes directly in the database table.

The function codes are defined in table `/SCWM/TFCOD_CAT`.

### 3.15.1 Predefined Function Codes in the RF Framework

Currently, there are several predefined function codes for decreasing application development effort. Function codes mean **logical** codes used in the step flow, and not simply the function codes triggered by buttons or function keys.

Function Code	Description of the Function Triggered
---------------	---------------------------------------

INIT	Starts the logical transaction; if an entry for the initial step and function code <code>INIT</code> is defined in table <code>/SCWM/TSTEP_FLOW</code> , this entry is the PBO for the first dynpro. If no entry is defined, the initial step is displayed in the foreground.
CLEAR	Clears the input field that currently contains the cursor. If you choose <code>CLEAR</code> twice without changing the position of the cursor, the system clears all of the input fields. This behavior can be customized in field <code>FLG_CLEAR_ALL</code> of table <code>/SCWM/TPRDV_CAT</code> . In the standard SAP system, this feature is activated. With <code>CLEAR</code> , the flow logic does not return from the screen. This means that <code>CLEAR</code> does not trigger a step flow.
BACK	Navigates flow logic to the previous foreground step. If you have defined PBO steps in table <code>/SCWM/TSTEP_FLOW</code> , however (such as the <code>INIT</code> step), the PBO steps are NOT reprocessed.
ENTER	
LIST	Displays a screen containing a list of possible entries for the current input field. Corresponds to a list-box display.
UPDBCK	Updates the data in the stack and returns to the previous foreground step. If you need to perform steps in addition to the main operation step, for example, exception handling to determine a new storage bin, the main operation data changes. If you leave the exception with <code>UPDBCK</code> , the system updates the stack data.
NEXTSC	Used when a screen is split. The next screen of the split screen can be accessed using this function code.
BUILD_MENU	Used in standard service step <code>MENU</code> .
PGUP	Used for automatic page up implementation.
PGDN	Used for automatic page down implementation.
YES	Used in standard service step <code>MESSAGE / QUERY</code> .
NO	Used in standard service step <code>MESSAGE / QUERY</code> .
MORE	Used for navigation with grouped buttons. The next button group is displayed using <code>MORE</code> . If you apply this to the last group, the system switches to the first group.
FULLMS	Displays error messages on a separate screen. Used to view the full text of an error message if the bottom line is not sufficient.
UNKNOWN	Used internally to handle unmapped function codes from the screen that are not defined in table <code>/SCWM/TSTEP_FLOW</code> .
UPDPST	Light synchronous posting.
CLSEMS	Clears message lines and displays the screen as standard.
CMPTRS	Ends a logical transaction. This function code must be set at the end of each logical transaction using the <code>SET_FCODE</code> method of class <code>/SCWM/CL_RF_BLL_SRVC</code> to continue in the defined way.

### 3.16 Assign Text to Function Code

You assign text to function codes in table `/SCWM/TOBJ_TXT`. The length of the function code text is defined in the display profile.

### 3.17 Create Services to Support Business Logic

A service is a function module that is assigned to a step flow definition. The function modules include the coding that is normally specified in the PBO and PAI modules.

The function module interface is restricted. Only CHANGING parameters are allowed. The parameters can contain structures and tables. Field parameters are not allowed.

Note: The function module of the last step of the logical transaction must call method `SET_FCODE` of class `/SCWM/CL_RF_BLL_SRVC`. Function code `CMPTRS` must be set with this function. Alternatively, you can set or process this function code in step flow `/SCWM/TSTEP_FLOW` in background mode.

```
* Call method of RF framework to mark end of transaction
/scwm/cl_rf_bll_srvc=>set_prmod('1').
/scwm/cl_rf_bll_srvc=>set_fcode( /scwm/cl_rf_bll_srvc=>c_fcode_compl_ltrans ).
```

### 3.18 Define State Catalogue

States identify relatively small differences in the same step behavior and presentation view. You must take into account that the state is a parameter of the step and you can load it with its own features. You can omit or add some functions (such as buttons and functions keys) in accordance with the state and verification profile, and define a specific screen for a particular state of the step.

We recommend that you change the behavior of the step in accordance with parameters with a state definition instead of doing so with a new step.

The state used is controlled by the content provider. Depending on your own rules, you set the state with method `/SCWM/CL_RF_BLL_SRVC=>SET_STATE`. The state is used in tables `/SCWM/TFCOD_PRF`, `/SCWM/TSTEP_SCR`, and `/SCWM/TVALID_PRF`. You can define new states in the Customizing activity *Define Steps in Logical Transactions* by choosing *Define Steps* → *Define States*. A state can only be defined for a step.

The framework uses the following predefined states internally:

- ☐ FIRST to show the first page of menu items.
- ☐ MIDDLE to show inner pages of menu items.
- ☐ LAST to show the last page of menu items.
- ☐ QUERY
- ☐ INFERR

Example: The system can display the logon screen for the user in three different states: after disconnection with attached worklist; after disconnection without attached worklist; and after normal logoff. The same step is used for all three states, defining specific function codes for each state: `DISCONNECT`, `RECONNECT`, or `CONNECT`.

### 3.19 Map Logical Transaction Step to Sub-Screen

Each step processed in the foreground must have a corresponding sub-screen and program.

You configure this in the Customizing activity *Define Steps in Logical Transactions* by choosing *Define Logical Transactions* → *Map Logical Transaction Step to Sub-Screen*.

Mapping data is stored in table `/SCWM/TSTEP_SCR`.

### 3.20 Define Function Code Profile

In the function code profile, you define the button and function key for the screen or step. You can also define an external reason code and disable the function code, button, or function key.

The buttons are assigned to the template at runtime.

If you want to only activate the function key and not display the button, leave the `PUSHB` field empty.

If you want to activate only the button and not a corresponding function key, leave the `FNKEY` field empty.

The text on the button can be maintained in the Customizing settings for RF in which the function codes are defined (if used).

If you want to use standard function codes such as `BACK` or `CLEAR`, you must define them in the function code profile. They are not automatically available. Be careful if you use additional states in your logical transaction. State `*****` is used as the default. This means that function codes that are not defined in your additional state are automatically added by the framework. If you want to avoid this, you can copy the entries with state `*****` and select field `FLG_DISABLE`. If you always work with custom states and not with state `*****`, you can delete

the entries with state \*\*\*\*\*.

Be aware that F10 cannot be used directly. This function key cannot be addressed directly in the GUI status. If you require F10 on the device, a workaround is available. Pressing F10 on the device triggers an escape sequence of, for example, SHIFT+F10. SHIFT+F10 is used in the function code profile and defined in the GUI status. Note, however, that this solution does not work in the SAPGUI.

The following function codes should be used in the standard SAP system and assigned to the following function keys:

Function Code	Function Key	Shortcut	Action
NEXT	F4	04	Jump to next screen (for example, from source to destination or from destination to end of transaction)
MORE	F5	05	Display next button sequence
CLEAR	F6	06	Clear input field / Clear all input fields
BACK	F7	07	Return to previous screen without saving entered data in data container
UPDBCK	F7	07	Return to previous screen and save entered data in data container
LIST	F8	08	Display possible data for the current field
FULLMS	F9	09	Display message on separate screen
ENT	ENTER		Default navigation

If you display buttons, only the non-standard functions are displayed (such as the detail screen). No buttons should be assigned to the function codes mentioned above except for NEXT (which is controlled by the content provider). The function code profiles are stored in table /SCWM/TFCOD\_PRF.

Note: If you need to display the standard functions, use the field *Standard Function Codes as Buttons* in the *Maintain Presentation Devices* transaction (/SCWM/PRDVC).

### 3.20.1 GUI Status Is Defined for the Template

The GUI status is defined at template level and is, therefore, valid for all sub-screens.

The buttons and function keys are dynamically excluded in accordance with the definition in /SCWM/TFCOD\_PRF. This means that in the GUI status, all necessary function keys must be defined in advance.

All function keys must be defined as *Application function* for functional type. Do not define them as *Exit Command*. *Exit Command* function keys are not currently supported.

### 3.20.2 Connect Screen Function Codes and RF Framework Function Codes

In the GUI status, the function keys are defined with the function codes. You have F1 to F10 for the corresponding function keys, ENT for ENTER, PGUP for PAGE UP and PGDN for PAGE DOWN. No buttons are defined in the GUI status.

On the template dynpro, the buttons are defined with the function codes PB1 to PB4.

The function codes used in the step flow are defined in table /SCWM/TFCOD\_CAT. Here you define more meaningful function codes such as BACK, ENTER, DETAIL, SAVE, and so on.

In table /SCWM/TFCOD\_PRF, you establish the link between the GUI function codes and the RF framework function codes and step flow.

APPLIC	LTRANS	STEP	STATE	SNCE	FCODE	PUSHB	FNKEY	Shortcut
--------	--------	------	-------	------	-------	-------	-------	----------



01	LTX1	STEP1	*****	01	DETAIL	PB1	F1	01
01	LTX1	STEP1	*****	01	CLEAR		F6	06
01	LTX1	STEP1	*****	01	BACK		F7	07
01	LTX1	STEP1	*****	01	FULLMS		F9	09
01	LTX1	STEP1	*****	01	ENTER		ENT	
01	LTX1	STEP2	*****	01	SPLIT	PB1	F1	01
01	LTX1	STEP2	*****	01	ZERO	PB2	F2	02
01	LTX1	STEP2	*****	01	NEST	PB3	F3	03
01	LTX1	STEP2	*****	01	CLEAR		F6	06
01	LTX1	STEP2	*****	01	BACK		F7	07
01	LTX1	STEP2	*****	01	FULLMS		F9	09
01	LTX1	STEP2	*****	01	ENTER		ENT	

Note that some columns are not displayed to provide a better overview. By defining the above table, you specify that in STEP1, only the first button (PB1 in the left-hand corner) is valid and visible with the function code `DETAIL`. In addition, the function codes `CLEAR`, `BACK`, and `FULLMS` are assigned to function keys and a shortcut value. The function code `ENTER` is assigned to the `ENTER` key without a shortcut value. In STEP2, you have the three buttons on the top, valid and visible, and assigned to the function keys `F1` to `F3`. The rest is the same as in STEP1.

### 3.20.3 Handle More Function Codes Than Available Buttons on a Screen or Step

If you have more function codes than available buttons on your screen or, in other words, on your step, you have the following option. In table `/SCWM/TFCOD_PR`, group your function codes with field `SEQNCE`. This field also indicates the sequence of the groups. In addition, each group must contain the function code `MORE`, which must be assigned to a function key. Do not assign `MORE` to a button. The RF framework will display a *greater than* symbol (>) automatically if more function codes than available buttons are defined. The symbol indicates to the user that more function codes are available. The user must know which function key triggers the `MORE` function code. The RF framework is responsible for presenting the correct group. After the last group, the first group is displayed again. Each function code to be processed must be defined in each group.

APPLIC	LTRANS	STEP	STATE	SEQNCE	FCODE	PUSHB	FNKEY	Shortcut
01	LTX1	STEP3	*****	01	DETAIL	PB1	F1	01
01	LTX1	STEP3	*****	01	SPLIT	PB2	F2	02
01	LTX1	STEP3	*****	01	ZERO	PB3	F3	03
01	LTX1	STEP3	*****	01	MORE		F5	05
01	LTX1	STEP3	*****	01	CLEAR		F6	06
01	LTX1	STEP3	*****	01	BACK		F7	07
01	LTX1	STEP3	*****	01	FULLMS		F8	08
01	LTX1	STEP3	*****	01	NEXT	PB4	F4	04
01	LTX1	STEP3	*****	01	PRINT		F11	11

01	LTX1	STEP3	*****	02	PRINT	PB1	F11	11
01	LTX1	STEP3	*****	02	NEXT		F4	04
01	LTX1	STEP3	*****	02	MORE		F5	05
01	LTX1	STEP3	*****	02	CLEAR		F6	06
01	LTX1	STEP3	*****	02	BACK		F7	07
01	LTX1	STEP3	*****	02	FULLMS		F9	09
01	LTX1	STEP3	*****	02	DETAIL		F1	01
01	LTX1	STEP3	*****	02	SPLIT		F2	02
01	LTX1	STEP3	*****	02	ZERO		F3	03

In this example, we have assumed a display profile with only four buttons. We have defined two groups, and all groups have the same function codes. There are function codes with a button assignment and function codes without a button assignment in each group. Note that function codes not defined in the actual sequence are not available and cannot be processed. You must define them without assigning a button.

### 3.20.4 Add Standard Function Codes as Buttons

Modern RF devices often have no physical keyboard and also no hardware function keys, but instead have touch-enabled displays. This means that the navigation can only be done by pressing a button on the display or having a virtual keyboard on the screen, which is often cumbersome to use.

Based on standard RF Customizing, touch-enabled displays cause the following challenges:

- Standard function codes such as CLEAR (clear field input value), BACK (go back one step), LIST (value help similar to F4 in desktop transactions), and FULLMS (show wrapped message on separate screen) are never available on a button
- Labels on buttons always contain the corresponding function key, for example, **F10** Print

This functionality is a generic approach without the need to change existing RF Customizing. The additional buttons are only added during runtime.

The *Maintain Presentation Devices* transaction (/SCWM/PRDVC) can control how standard function codes are automatically added to the button groups during runtime. The following options are available:

Don't Add as Buttons	This standard function codes are only available by function key.
Add at End of Button Groups	The standard function codes appear after all other function codes assigned in RF Customizing.
Add at Start of Button Group	The standard function codes appear before all other function codes assigned in RF Customizing.
Sort Buttons According to Function Key	The standard function codes appear according to their function key (between F4 and F10).
Add Back and Clear in First Button Group	Standard function codes BACK and CLEAR are at the beginning and the remaining standard function codes are added at the next button group.
Add with Customer Implementation	Business Add-In (BAI) <i>Addition of Standard Function Codes as Buttons</i> (/SCWM/EX_RF_ADD_FC_AS_PB) is called.

If you select one of the options, the function key information is removed from the button text.

New function code `GTEXCP` is introduced in RF Customizing for the RF framework only. This function code is added as the fifth standard function code that needs to be added as a button. This function code displays a list of valid exceptions without the need to enter an exception code such as `LIST` but by pressing a button. The button is only available if the RF Customizing function code profile contains an entry with the *Exception* (Shortcut is an Exception) checkbox selected for the current logical transaction and step. If you choose the button, the RF framework uses internal exception `LIST` to determine the external exception code to display valid exception codes. This exception code is moved into the shortcut field and the function code for exceptions is triggered. Then the list of valid exceptions is displayed automatically (`/SCWM/CL_RF_BLL_SRV=>TRIGGER_EXCEPTION_CODE_LIST`). You can switch off this functionality with method `/SCWM/CL_RF_BLL_SRV-SET_NO_EXCEPTION_LIST`.

Note that the system can't display messages on the bottom line because the message hides the buttons, which then prevents further navigation, for example, leaving the transaction.

### 3.20.5 Switch Off Function Codes Not Supported in SAP S/4HANA Cloud

As SAP S/4HANA Cloud and SAP S/4HANA share the same RF Customizing but some functionality is not available in SAP S/4HANA Cloud, some function codes are switched off by coding in `/SCWM/CL_RF_BLL_DB-CHECK_FCODE_IS_NOT_IN_CLOUD`.

If a function code is switched off there, the corresponding button is not visible.

### 3.20.6 Switch Off Fields Not Supported in SAP S/4HANA Cloud

As SAP S/4HANA Cloud and SAP S/4HANA often share the same RF transaction but some details are not available in SAP S/4HANA Cloud, some fields, for example, the hazardous substance indicator or catch-weight indicator, are switched off by coding in `/SCWM/CL_RF_DYNPRO_SRV-CHECK_FIELD_IS_NOT_IN_CLOUD`. Then there's no need to copy the RF transaction and create one specific for SAP S/4HANA Cloud.

## 3.21 Define Step Flow

The step flow determines the business process flow and the corresponding content provider function modules. Only function modules can be used. Although function modules can be combined in the standard SAP system, there should only be one function module for the PBO (Process Before Output) and one for the PAI (Process After Input). The naming convention is `/SCWM/RF_<Process_<Step>_PBO` or `/SCWM/RF_Process_Step_PAI` (for example, `/SCWM/RF_PTWY_SOURCE_PBO` or `/SCWM/RF_PICK_CHECK_PAI`). It is clear that within these function modules, you can call other function modules that can be reused. Having only one function module makes Customizing easier and also helps to follow the step flow.

In the step flow definition, you define the transaction step sequence taking into account the function code applied by the user. Steps may be displayed in the foreground or processed in the background as determined in Customizing. Steps can be combined. If you combine steps, the step flow is interrupted only by error messages. Be careful with error messages issued from a function module that is processed before the screen is displayed (PBO). The message is displayed on the next screen and not on the previous one. This means that the user can proceed without correcting the old error. The error should be checked again in the PAI module.

The step flow is defined in table `/SCWM/TSTEP_FLOW`.

PRMOD 1 -> Background processing

PRMOD 2 -> Foreground display

#### 3.21.1 PBO of Initial Screen After Menu Selection

The table entry in PBO of the initial screen should appear as follows:

APPLIC	PRES_PRF	LTRANS	STEP	FCODE	FMODUL	SSTEP	PRMOD	FCODE_BCKG
01	****	LTX1	STEP1	INIT	FM1_PBO	STEP1	2	

For logical transaction `LTX1` in step `STEP1`, once the transaction has been triggered from the menu function module, `FM1_PBO` is processed and the screen is displayed.

It is hardcoded that the function code for the first function module call must be `INIT`.

### 3.21.2 PAI of Screen and Direct Display of Next Screen

The table entry in PAI should appear as follows:

APPLIC	PRES_PRF	LTRANS	STEP	FCODE	FMODUL	SSTEP	PRMOD	FCODE_BCKG
01	****	LTX1	STEP1	ENTER	FM1_PAI	STEP2	2	

For logical transaction `LTX1` in step `STEP1`, after the `ENTER` function code has been triggered, function module `FM1_PAI` is processed and the new screen assigned to `STEP2` is displayed.

### 3.21.3 PAI of Screen and PBO of Next Screen

In PAI of screen 1 and PBO of screen 2, the table entry should appear as follows:

APPLIC	PRES_PRF	LTRANS	STEP	FCODE	FMODUL	SSTEP	PRMOD	FCODE_BCKG
01	****	LTX1	STEP1	ENTER	FM1_PAI	STEP2	1	BCK01
01	****	LTX1	STEP2	BCK01	FM2_PBO	STEP2	2	

For logical transaction `LTX1`, function module `FM1_PAI` is processed in step `STEP1` after the `ENTER` function code has been triggered. `FM2_PBO` is then processed in the background and the new screen from `STEP2` is displayed.

### 3.21.4 Call of Common Screen from Several Screens During Transaction

If you want to call one screen from several steps of your logical transaction, you must only ever leave the screen using the function code `BACK` or `UPDBCK`. The internal call stack is only updated correctly with `BACK` and `UPDBCK`. If you want to leave the screen with another function code for any reason, create an entry in table `/SCWM/TSTEP_FLOW` as described below.

Additionally, you define which step the verification is to carry out beforehand. If you have more steps, only set the *Verification* indicator once.

Example: WT detail screen called from source screen and destination screen.

APPLIC	PRES_PRF	LTRANS	STEP	FCODE	FMODUL	SSTEP	PRMOD	FCODE_BCKG
01	****	LTX1	STEP1	ENTER		STEP1	1	BACK

With this definition, the detail screen is left with `ENTER` and function code `BACK` is processed in the background.

### 3.21.5 Customizable ENTER / Set Next Step Dynamically Using the CP

It should be possible that the CR (Carriage Return) received from a scanner or the user by pressing `ENTER` is redefined to act like a combination of several function keys, for example, `F1` (`SAVE`) and `F4` (`NEXT`). `ENTER` should respond as follows:

- ☐ If you are not in the last input field, the cursor is positioned in the next input field (either verification or input field).
- ☐ If you are in the last input field but not on the last open WT, the actual WT is saved and the next open WT is displayed (source or destination).
- ☐ If you are in the last input field and on the last open WT, the actual WT is saved and comes from the source screen. The destination screen of the first TO is displayed. The transaction is finished when the last open WT is closed and confirmed by the destination screen.

Example: The `ENTER` key is defined as function code `ENTER`. The `ENTER` key triggers navigation between the input fields and posting to the database. If all fields are entered, the step flow is divided into three steps: navigation, check of the data entered, and posting to the database.

APPLIC	PRES_PRF	LTRANS	STEP	FCODE	FMODUL	SSTEP	PRMOD	FCODE_BCKG
--------	----------	--------	------	-------	--------	-------	-------	------------

01	****	LTX1	STEP1	ENTER	FM_NAV	STEP1		
01	****	LTX1	STEP1	SOURCE		STEP2	2	
01	****	LTX1	STEP1	DEST		STEP3	2	

It is important that the processing mode (PRMOD) and the background function code (FCODE\_BCKG) are initial.

These fields are filled in function module FM\_NAV with the following two methods:

□ /SCWM/CL\_RF\_BLL\_SRVCS=>SET\_PRMOD

□ /SCWM/CL\_RF\_BLL\_SRVCS=>SET\_FCODE

Example coding for the navigation function module:

\* If only assigned ones were found, we must jump to destination

IF lv\_enqueue IS INITIAL.

    /scwm/cl\_rf\_bll\_srvcs=>set\_prmod('1').

    /scwm/cl\_rf\_bll\_srvcs=>set\_fcode('DEST').

    EXIT.

ELSE.

\* We found un-assigned ones and are continuing with source

/scwm/cl\_rf\_bll\_srvcs=>set\_prmod('1').

    /scwm/cl\_rf\_bll\_srvcs=>set\_fcode('SOURCE').

ENDIF.

### 3.21.6 Additional Information

All actions that can be counted as PBO of STEP2 in connection STEP1 →STEP2 must be attached to initial code of STEP2. Otherwise they will be attached to STEP1. BACK to STEP1 will recover STEP1 with all changes not relevant to STEP1.

**Example:**

APPLIC	LTRANS	STEP	FCODE	FMODUL	SSTEP	PRMOD	FCODE_BCKG
01	LTX1	STEP1	FCODE_X	MODULE_X	STEP2	1	INIT_2
01	LTX1	STEP2	INIT_2	MODULE_INIT_2	STEP2	2	

MODULE\_X: actions associated with STEP1 because the module is called before the next foreground step is processed. If STEP2 works with another table and you set the new table name too early (for example, in MODULE\_X), this change is stored in the data for STEP1. When you return from STEP2, the data is restored and STEP1 works on the wrong table.

Therefore, the step flow should be as follows:

APPLIC	LTRANS	STEP	FCODE	FMODUL	SSTEP	PRMOD	FCODE_BCKG
01	LTX1	STEP1	FCODE_X		STEP2	1	INIT_2
01	LTX1	STEP2	INIT_2	MODULE_X	STEP2	1	INIT_3
01	LTX1	STEP2	INIT_3	MODULE_INIT_2	STEP2	2	

In general, first change the step and then configure the data access or setting for this step.

### 3.22 Set Default Navigation at Transaction End

The default navigation is determined at the end of a logical transaction. The navigation allows the following handling:

Value	Meaning
0	User decision
1	Main menu
2	Last menu
3	Same transaction; Restart logical transaction

The default definition is defined in table /SCWM/TTRNS\_NAV.

**Note:** To trigger the default navigation, the function module of the last step of the logical transaction should include the call of method SET\_FCODE of class /SCWM/CL\_RF\_BLL\_SRVC. Function code CMPTRS must be set with this function. Alternatively, you can set or process this function code in the step flow /SCWM/TSTEP\_FLOW in background mode.

```
* Call method of RF framework to mark end of transaction
/scwm/cl_rf_bll_srvc=>set_prmod('1').

/scwm/cl_rf_bll_srvc=>set_fcode( /scwm/cl_rf_bll_srvc=>c_fcode_compl_ltrans ).
```

### 3.23 Set Verification Profile

Verification fields must be included when the sub-screens are created. The verification fields in the dynpro must be taken from the same structure as the data fields. The verification field should follow directly after the origin field without a space in between.

In the verification profile, you assign the verification field to the comparing data field including the data structure. The *translation* method for the barcode (for example, to support EAN128 in EM function module /SCWM/RF\_EAN128\_SPLIT\_VALID) is implemented and explicit disabling has been defined here. If you do not need a one-to-one verification (for example, if the material can be identified by the material number and EAN/UPC number), you can define a function module that carries out the verification instead of the framework.

Be careful if you use additional states in your logical transaction. State \*\*\*\*\* is used by default. This means that verification fields that are not defined in your additional state are automatically added by the framework. If you want to avoid this, you can copy the entries with state \*\*\*\*\* and select field FLG\_DISABLE. If you always work with your own states and not with state \*\*\*\*\*, you can delete the entries with state \*\*\*\*\*.

#### 3.23.1 Verification

Define the verification fields in your dynpro. The verification fields are always character-based with a length of 255 characters. Screen group 3 for these fields must be filled with 002. This activates the verification fields and enables the RF framework to deactivate the verification field after successful verification. If the screen group does not contain 002, the fields will **never** be verified.

In table /SCWM/TVALID\_PRF, assign the verification field to the field that contains the comparing data value.

APPLIC	LTRANS	STEP	STATE	VRFVAL_TABNAME	VRFINP_FLDNAME	VRFVAL_FLDNAME
01	LTX1	STEP1	*****	/SCWM/S_RF_PROTO	NLPLA_VERIF	NLPLA
01	LTX1	STEP1	*****	/SCWM/S_RF_PROTO	CHARG_VERIF	CHARG

Be aware that some columns are not displayed in order to improve the overview.

In the table definition above, you have defined that in STEP1, you have two verification fields named /SCWM/S\_RF\_PROTO-NLPLA\_VERIF and /SCWM/S\_RF\_PROTO-CHARG\_VERIF. The data of the first verification field is checked against the data in field /SCWM/S\_RF\_PROTO-NLPLA and the second is checked against /SCWM/S\_RF\_PROTO-CHARG.

In field `FLG_VERIF` of table `/SCWM/TSTEP_FLOW`, you define the step before which verification is to be carried out. Note that verification must only be carried out once. If you have more than one step, only one step (normally the first) should be indicated as *Verification relevant*.

Verification is carried out automatically in the RF framework in method `/SCWM/CL_RF_BLL_SRVC=>CHECK_VERIF_PRF`. The field with the comparing data value must be in a structure defined in table `/SCWM/TPARAM_CAT`.

If you add a function module, verification control is based on the content provider and the check must be carried out in the function module. As an **IMPORT** parameter, the function module must have a structure named `IS_VERIF_PRF` of type `/SCWM/S_VERIF_PRF_EXT` and a field named `IV_FLG_VERIFIED` of type `XFELD`. As an **EXPORT** parameter, a field must be created with the name `EV_FLG_VERIFIED` and type `XFELD`. Optionally, you can have **CHANGING** parameters in the same way as the other function modules that belong to the content provider. `/SCWM/S_VERIF_PRF_EXT` contains all information of the current verification field from table `/SCWM/TVALID_PRF` and the conversion exit for this field. `IV_FLG_VERIFIED` is selected if the framework already carried out a positive verification before the function module was called. `EV_FLG_VERIFIED` contains the return value. X indicates a positive verification and an initial value indicates a negative verification. Note that the function module itself does not trigger an error message. The standard error message is triggered by the framework.

If verification is not successful, error message `/SCWM/UI_RF:020` (Invalid verification of &1) is processed. If the verification fields are empty, error message `/SCWM/UI_RF:021` (Enter verification of &1) is processed.

In field `FLG_VERIF` of table `/SCWM/TSTEP_FLOW`, you can specify that verification is carried out before the next step or function module is processed. If none of your steps or sub-steps contain the verification indicator, no verification is carried out.

Note that the verification fields must be longer if you verify using barcode scanning and you use concatenated barcodes such as EAN128. Otherwise, the scanned barcode information may be truncated because of the limitation to the input field length.

In the RF framework application table (`/SCWM/TAPPL_CAT`), you can define a function module to influence or control the verification fields based on the actual application data. For example, if you pick from storage type 0001, you want to verify fields other than by picking from storage type 0002. The RF transaction opens all verification fields by default. You can use the function module to deactivate verification fields. The example function module is `/SCWM/RF_WME_SET_VERIFICATION`.

### 3.24 Presentation Device Catalog

In the catalog, you define the single RF device and its characteristics such as the display profile, presentation device type, data entry type, and function key quantity. You also define indicators for the **CLEAR ALL** function, enabling shortcuts to the templates and the default device, as well as the sounds that are issued when a warning message or success message appears (if you're using ITSmobile). The device catalog is stored in table `/SCWM/TPRDV_CAT` and can be maintained in the Maintain Presentation Devices transaction (`/SCWM/PRDVC`).

If you're using SAP GUI for HTML and want sound, you must select a sound scheme for your presentation device. The sound schemes are delivered by SAP and are the same as the sounds used by SAP GUI. They can't be changed and you can't use your own sounds. The sound scheme is implemented **AFTER** the logon step when the customer has entered the presentation device (see function module `/SCWM/RSRC_LOGON`).

To have sound already during the logon step, you can do the following (see function module `/SCWM/RSRC_USER_DEF_SET_GET`):

- Set a sound scheme in the start URL with parameter `~itsmobile_ng_sound_scheme`.
- Define a sound scheme in the default presentation device. This overrides the URL sound scheme.

Notes:

If you haven't selected a sound scheme for your presentation device, there may still be sound. For example, if the URL contains a sound scheme but the presentation device has no sound scheme, the system uses the sound scheme of the URL. If you don't want any sound, you must explicitly specify the sound scheme to *A (No Sound)*.

Typos in the sound scheme of the URL means that there's sound.



## 4 LAYOUT

The following information is a general proposal for the screen layout and is intended to help developers to design the screens. This information does not address all of the open issues. If you have additional information that may be of interest to other developers, contact the author and request that the document be updated.

### 4.1 Screen

The screen size for the sub-screen is 7x40. Make sure that you use this space. It is easier for customers to delete a field than to add one, and so it is advisable to create a random field if additional space is available.

The fields should start at line 1, column 1.

The fields on the screen should be arranged line by line. This means that empty lines should be omitted (not implemented).

### 4.2 Fields

The RF screens use different (shorter) field labels than the normal UIs. We have therefore created data elements for RF based on the domains from standard data elements.

Use the 10-character field label if possible.

If no suitable field is available, use the following procedure to obtain one:

1. Create your own data element using the naming convention `/SCWM/DE_RF_XXXXXXX` and domain according to the data element.
2. Define the field labels with a length of 4, 6, 8, and 10 characters. For the field label with 10 characters, search for a standard term in SAPterm (in the Corporate Portal, use the quick link `/sapterm`). If you find abbreviations in SAPterm that can be entered in the field sizes, use the standard abbreviation. If there is no abbreviation, you must create your own.
3. Add the new data element to structure `/SCWM/S_RF_SCRTXT`.
4. Add the new data element to your own structure.
5. Use the field of your structure on your screen.

Not all of the fields have a field label. For example, *Storage bin* contains the fields *Storage type* and *Storage bin*.

Field attributes are set directly in the dynpro. You can use screen group 003 with values 001 and 002. The framework still offers methods of changing field attributes at runtime. These methods can be called in your function module that is processed before the screen is displayed. You can activate or deactivate the input option, the required option, and the visible option. However, if you want to use this feature, note the impact on potential customer changes later on.

Input fields must be defined without *Search Help* and *Foreign Key Check*. If you want the user to enter data in an input field, you must set the *Input* option to *Obligatory*. The framework then checks this option and displays error `/SCWM/UI_RF_035`: "Enter required field". Note that the verification check and required input check are carried out only if the *Verification* indicator is selected in the step flow.

Verification fields must be defined with value TRUE for the property *BarcodeInput*. You will find the property in the layout editor on the field attributes when you choose the icon with the blue arrow (->). This permits special characters (Hex values) in a barcode, which are normally filtered by SAPGUI.

Verification fields follow directly after the original field without a space in between.

#### 4.2.1 Field Length

Quantity fields should use domain `/SCWM/DO_QTY_VERIF`. This domain uses conversion exit `QNTY1`, which shortens the character-based field from 255 characters to 21 characters. The number can contain 17 digits plus 3 decimals. On the screen, limit the output length to 11 characters and set the field to scrollable.

The product number must be defined with 18 characters. Use data element `/SCWM/DE_RF_MATNR`, which is based on domain `/SCWM/DO_RF_MATNR`. This domain limits the output length to 18 characters. The material short text should be defined with 20 characters. We recommend that you display the material short text whenever possible, depending on the space on the screen.

Special stock is displayed with the category, the document number, and the item number.

The warehouse request must be defined with 20 characters, the item number with 6 characters, and the batch



number with 10 characters.

Verification fields have a length of 255 characters but only one visible character. Input fields have a length of 255 characters to support barcode scanning into these fields.

The content provider is responsible for the conversion. This means that all fields with a GUID or a timestamp will be shown in readable fields (for example, MATNR instead of MATID) and must be converted before they are displayed (in PBO) and after the return from the screen (in PAI) by the content provider.

## 5 PROGRAMMING INFORMATION

### 5.1 Posting

Data for the RF transaction must be posted occur online. This allows the user to react to any errors that may occur during posting. We recommend that data is posted in `UPDATE TASK` but the commit should be carried out by `COMMIT WORK AND WAIT`. Although errors may occur, this process ensures that the order within the posting is not changed.

### 5.2 Exception Handling and Using Shortcuts

The `SHORTCUT` field from structure `/SCWM/S_RF_SCRELM` is part of the template. The field is four characters long, although only two of these characters are displayed. You can use the field for navigation purposes by entering a shortcut value, and you can also use it to trigger exceptions by entering an exception code. You can define the field as optional or mandatory using the `FLG_SHORTCUT` indicator in table `/SCWM/TPRDV_CAT`. If you define the field as optional, it is not considered in the default navigation. This means that choosing `ENTER` on the last input field of the sub-screen triggers the step flow. You must navigate to the field (for example, to enter an exception) manually using the `TAB` key. If you define the indicator as mandatory, the cursor is always set to the field once the last input field on the sub-screen has been completed. The user must then press `ENTER` again to trigger the step flow.

#### 5.2.1 Navigation

In the `FLG_SHORTCUT` field of table `/SCWM/TPRDV_CAT`, you can control whether the shortcut function is activated. If the indicator is selected (mandatory), navigation is triggered when the user presses `ENTER` in the shortcut field. If the indicator is not selected, navigation is triggered when the user presses `ENTER` on the last field of the screen. Reaching the shortcut field, which is the very last field, is not necessary. You must then navigate using the function keys.

Furthermore, to mark the flag you must assign the corresponding shortcut values in table `/SCWM/TFCOD_PRF` to the function codes that are to be triggered. Figures 1 to 10 are reserved for navigation. The figures reflect the function keys F1 to F10. Use the following assignment in the standard SAP system:

FCODE	Function key	Shortcut
MORE	F5	05
CLEAR	F6	06
BACK or UPDBCK	F7	
LIST	F8	08
FULLMS	F9	09

You can use the `FLG_QUICK_ENTER` indicator to suppress the jump to the shortcut field even if it is visible. The indicator is part of table `/SCWM/TSTEP_SCR` and can be set in the screen management tool (transaction `/SCWM/RFSCR`). However, you must note that the PAI function module is called for each field. Therefore, the programmer must ensure that the posting (such as WT confirmation) is not called too early.

## 5.2.2 Exceptions

If you want to trigger exceptions, you can use methods from the *Exception handler*. The `GET_EXCEPTION_CODE` method returns a list of possible exceptions in your business context. The `VERIFY_EXCEPTION_CODE` method verifies the exception code and obtains the internal exception code, which you can use for your internal responses to the exception. Method `PROCESS_EXCEPTION_CODE` is triggered for asynchronous exception processing.

In your step flow (`/SCWM/TSTEP_FLOW`), you must make provisions for a function code assignment with a shortcut value `****`. This function code and the function module assigned to it is processed by the framework. The exception should be checked in this function module. Depending on the internal exception code, you can then set the follow-up step (if necessary). The exception can either be posted in this function module or at a later point. This must be specified by the developer.

## 5.3 Differences

Differences are handled on a separate screen that has the same appearance. If you want to implement a new type of difference, we recommend that you use the standard screen.

## 5.4 Support LIST Functions

The framework offers a function whereby possible entries for an input field are displayed for the user.

The content provider must communicate the possible fields and the values that can be selected to the framework. Obsolete values can be reset using method `/SCWM/CL_RF_BLL_SRVC=>INIT_LISTBOX` (field name). Method `/SCWM/CL_RF_BLL_SRVC=>INSERT_LISTBOX` (field name, value, and text) enables you to add a value to the list box. You must call this method for each possible value. In the function code profile, you must assign function code `LIST` to a function key and/or button. The standard function key is `F8`. Users can then press the function key when the focus is on the field. The framework displays a new screen on which users can select a possible value. The value is then transferred to the input field.

## 5.5 Display of Text (from Delivery or Hazardous Material)

A standardized method of retrieving and displaying text from the hazardous material master and delivery is available. Function module `/SCWM/RF_TEXT_GET_AND_SET` reads the texts and transfers them to the RF framework (using method `/SCWM/CL_RF_BLL_SRVC=>SET_RF_TEXT`).

You can then display the text by pressing `F9` (function code `FULLMS`). The RF framework displays the text in a step-loop. If an error message is to be displayed, first the error message is displayed and then the text is displayed (from the error text screen) when you press `F9` again. An indicator is also displayed on the application screen to inform the user that text is available.

## 5.6 Methods Available to the Content Provider

### 5.6.1 Methods into the Framework

- `/scwm/cl_rf_bll_srvc=>set_prmod( '1' )` to set the processing mode of the next step in the step flow. '1' = Background; '2' = Foreground
- `/scwm/cl_rf_bll_srvc=>set_fcode( 'DEST' )` to set the function code to determine the next step flow
- `/scwm/cl_rf_bll_srvc=>set_state( '*****' )` to set the state
- `/scwm/cl_rf_bll_srvc=>set_field( 'WHO' )` to set the cursor to a specific field
- `/scwm/cl_rf_bll_srvc=>init_screen_param( )` to reset the data container used. Resets only the name, not the data itself
- `/scwm/cl_rf_bll_srvc=>set_screen_param( 'PICKPT' )` to introduce the data container used
- `/scwm/cl_rf_bll_srvc=>set_scr_tabname( 'TT_PICKPT' )` to introduce the table data container used
- `/scwm/cl_rf_bll_srvc=>set_line( 1 )` to set the actual / beginning line in the table data container used
- `/scwm/cl_rf_bll_srvc=>init_listbox( '/SCWM/S_RF_PICKPT-HUENT' )` to reset the data assigned to the given listbox
- `/scwm/cl_rf_bll_srvc=>insert_listbox( '/SCWM/S_RF_PICKPT-HUENT', 'X', 'HU-Entnahme' )` to set a value for the given listbox. For additional data, call the method again.
- `/scwm/cl_rf_bll_srvc=>set_screlm_required_on( '/SCWM/S_RF_PICKPT-VLPLA' )` to activate the

required field attribute for the given field

- /scwm/cl\_rf\_bll\_srvc=>set\_screlm\_required\_off('/SCWM/S\_RF\_PICKPT-VLPLA') to deactivate the required field attribute for the given field
- /scwm/cl\_rf\_bll\_srvc=>set\_screlm\_invisible\_on('/SCWM/S\_RF\_PICKPT-VLPLA') to activate the hidden field attribute for the given field
- /scwm/cl\_rf\_bll\_srvc=>set\_screlm\_invisible\_off('/SCWM/S\_RF\_PICKPT-VLPLA') to deactivate the hidden field attribute for the given field
- /scwm/cl\_rf\_bll\_srvc=>set\_screlm\_input\_on('/SCWM/S\_RF\_PICKPT-VLPLA') to activate the input field attribute for the given field
- /scwm/cl\_rf\_bll\_srvc=>set\_screlm\_input\_off('/SCWM/S\_RF\_PICKPT-VLPLA') to deactivate the input field attribute for the given field
- /scwm/cl\_rf\_bll\_srvc=>set\_flg\_stack('X') to set a new stack level. This can be used if you want the framework to add a new stack level to its internal stack.
- /scwm/cl\_rf\_bll\_srvc=>message( ' ', '/SCWM/UI\_RF, 'S', 'xxx' ) to display a message of type S or I.
- /scwm/cl\_rf\_bll\_srvc=>set\_flg\_dequeue\_all( ) to instruct the framework to carry out a DEQUEUE\_ALL
- /scwm/cl\_rf\_bll\_srvc=>set\_rf\_text( lt\_text\_table ) to transfer the read text to the framework

## 5.6.2 Methods out of the Framework

- /scwm/cl\_rf\_bll\_srvc=>get\_step( ) to obtain the actual step
- /scwm/cl\_rf\_bll\_srvc=>get\_fcode( ) to obtain the actual function code
- /scwm/cl\_rf\_bll\_srvc=>get\_line( ) to obtain the actual line number
- /scwm/cl\_rf\_bll\_srvc=>get\_state( ) to obtain the actual state

## 5.7 Global Variables

Most RF-specific function groups contain global variables. This could cause a problem if a customer program calls an RF function module directly, but within the FM, processing uses a global variable. Essentially, the FM has initial value if it is called from a customer program.

For each RF-specific function group, a new interface is created to set and get the global variables from the customer program. The name for the interface is created as follows:

- /SCWM/RF\_<process>\_SET\_GLOBVAR

This FM is responsible for setting the value of the global variable from the customer code, for example, /SCWM/RF\_PACK\_SET\_GLOBVAR, /SCWM/RF\_PICK\_SET\_GLOBVAR, and so on.

- /SCWM/RF\_<process>\_GET\_GLOBVAR

This FM is responsible for retrieving the value of the global variable from the standard code, for example, /SCWM/RF\_PACK\_GET\_GLOBVAR, /SCWM/RF\_PICK\_GET\_GLOBVAR, and so on.

### Use:

You have a customer-developed FM, within which an FM is called that belongs to the standard RF code. The standard FM contains a global variable that is updated, and the customer wants to use the updated value.

```
Z_RF_PICK_PIMTTO_PA1
...
lv_buscon = 5.
CALL FUNCTION /SCWM/RF_PICK_SET_GLOBVAR
IMPORTING
    iv_buscon = lv_buscon
CALL FUNCTION /SCWM/RF_PICK_PIMTTO_PA1
```

CHANGING

...

```
CALL FUNCTION /SCWM/RF_PICK_GET_GLOBVAR
```

```
EXPORTING
```

```
iv_buscon = lv_buscon
```


The customer has set the global variable in the customer-developed FM, the value is transferred to the standard FM, the FM /SCWM/RF\_PICK\_PIMTTO\_PAI changes the value of *buscon*, and the customer can then retrieve the changed value with FM /SCWM/RF\_PICK\_SET\_GLOBVAR.

## 5.8 Display Technical Data on GUI Title of RF UI

On the RF UI, you can display technical data by pressing CTRL+SHIFT+F1.

This function works only on SAPGUI. A request was submitted to provide technical information on the ITS as well, although the information that can be supplied is limited. The following data can be displayed in the ITS environment:

- ☐ Actual logical transaction
- ☐ Actual step
- ☐ Screen info



To obtain the technical information, you must set a user parameter by choosing *System* → *User Profile* → *Own Data*.

On the *Parameters* tab page, enter the parameter ID /SCWM/RF\_TECH\_TITLE and set the value to X.

If the user parameter is available on the standard user interface, the RF UI appears as follows:

**PISYSG PIHUIN /SCWM/SAPLRF\_PICKING 0200**

WO No. 210381 AA PInHUs 0

Pick-HU Pack. Mat. LP

F1 WOD... F2 HUCr F10 Prnt F4 Next

## 5.9 Hard-Coded Logical Transaction

Some RF function modules read the actual logical transaction to determine the next processing step. This behavior is hard-coded and means that the standard FM cannot be reused.

If you want to reuse standard RF function modules, see SAP Note 1521250.

### Procedure:

You create a custom picking transaction, for example, ZPINEW.

During the custom process, you want to use standard navigation with FM /SCWM/RF\_PICK\_NAVIGATION. At the beginning of the process, you specify the logical transaction that is to be simulated during the process with method /scwm/cl\_rf\_bll\_srvc=>set\_ltrans\_simu('PISYSG'). When any standard code is executed and the actual transaction checked, the simulated logical transaction is returned.

The simulated logical transaction can be changed at any time during the process.

The simulated logical transaction can be checked on the technical data screen, which can be accessed by pressing CTRL+SHIFT+F1.

RF Screen - Enhancement Trigger Dialog

---

**RF Screen - Technical Information**

Application	01		
Display Profile	**		
Present.Profile	****		
Prsn.Profile	**		
Log.Transaction	ZPINEW	Simulated	PISYSG
Step	PIPLHU		
State	PLHU		
Screen Sequence	01		
Screen Program	/SCWM/SAPLRF_PICKING		
Screen Number	301		
Pushb.Qty	04		
Func. Key Qty	**		

---

**Modification Options**

☒ Modify Screen  
☐ Split Screen  
☐ Undo Modifications  
☐ Start Screen Painter  
☐ Start Menu Manager

Method `/scwm/cl_rf_bll_srvc=>set_ltrans_simu` has a new optional parameter: `IV_FOLLOW_UP`. If you set the flag, it means when the RF FW try to get the customizing of the custom logical transaction, then it will use the real logical transaction name, instead of the simulated logical transaction.

#### Example:

You create new custom picking transaction PIZZWO. You want to use the standard logic for most cases, but for step PIHUIN, you want to use a custom screen, validation, step-flow, and function codes.

- Flag `IV_FOLLOW_UP` is not set, but the simulation is set to logical transaction PIBWHO. The system tries to collect all the customizing according to the simulated transaction, in this case the PIBWHO. So, if you want to add a new screen, then you must add it to the PIBWHO. If there is already a standard screen, then you must overwrite it and you will lose the original entry.
- Flag `IV_FOLLOW_UP` is set, then system collects the customizing under the real logical transaction PIZZWO. If there is nothing, check the PIZZ\*\*, PI\*\*\*\*\* and \*\*\*\*\*. This enhancement allows you to change the necessary step and keep the standard entries untouched so you can add your changes to the new logical transaction only.

Briefly: The system reads the following Customizing:

- Step-flow
- Function codes
- Screens
- Validation profile

If `IV_FOLLOW_UP` is set, then the real logical transaction is used.

If `IV_FOLLOW_UP` is not set, then the simulated logical transaction is used.

## 5.10 BAdIs Used to Enhance RF Framework Customizing



The RF framework already offers a huge flexibility to adopt EWM-standard RF transactions to customer needs. But all this flexibility is based on new and sometimes complex Customizing entries in different parts of the RF framework.

If customers copy Customizing entries of the standard RF transaction into a customer namespace, they can't make use directly of any new functionality (for example, new steps) added to the standard RF transaction.

In addition, the RF framework is warehouse-independent. It can be influenced only at top-level (presentation profile) for a warehouse. But sometimes customers only want to have small changes to the RF transactions and don't want to create a new set of Customizing for its presentation profile.

Customers want to integrate their own Customizing into the RF framework, controlling step flow, function code profile, or RF sub-screen determination.

Customers want to use the same RF transaction with different default values or field control without the need to add or copy Customizing.

## Concept

Based on the requirements, mentioned above, some new BAdIs are created with SAP S/4HANA 2021. They are all part of enhancement spot /SCWM/ES\_RF\_CUST.

BAdI	Description
/SCWM/EX_RF_CHANGE_FCPRF	BAdI: Change of Function Code Profiles
/SCWM/EX_RF_CHANGE_SFLOW	BAdI: Change of RF Step Flow
/SCWM/EX_RF_CHANGE_STEPSCR	BAdI: Change of Step Screen
/SCWM/EX_RF_CHANGE_TRNSNAV	BAdI: Change of Inter-Transaction Flow
/SCWM/EX_RF_CHANGE_VALIDPRF	BAdI: Change of Validation Profiles

For more information, see the BAdI and interface documentation.

Note: The BAdIs have warehouse number as filter criteria. As the RF framework don't know application data, we use function module /SCWM/RSRC\_RESOURCE\_MEMORY to get the warehouse entered during RF logon. In addition, we use function module /SCWM/RSRC\_USER\_GET to get the warehouse from table /SCWM/USER before the user entered a warehouse during RF logon. This is needed, for example, to control the function code profile when the RF logon screen is shown.

## 6 USING THE TOOLS PROVIDED

### 6.1 Menu Manager

You launch the menu manager using transaction /SCWM/RFMENU or from Customizing. For more information, see RF Framework Customizing Overview.

You use the menu manager to manage (create, delete, and change) customer menus.

The selection screen includes application, presentation, and personalization profiles and shows the screen size.

The first three parameters determine the menu hierarchy. The user can create, copy, and delete the menu hierarchy on the selection screen. In order to change the hierarchy, the user must choose *Change* and enter the screen of menu maintenance.

This screen is split into 2 parts: the left-hand part includes menu building blocks (menu and logical transactions) and the right-hand part includes the menu hierarchy.

Initially, the system displays the hierarchy of the main menu. The user can change the hierarchy as follows:

- ☐ Selecting an element in the left-hand ALV and choosing *Add as Sub Node*
  - If a tree menu is selected, a new item will be added to it.
  - If no tree menu item is selected, a new item will be added to the upper menu.
- ☐ Selecting an element in the left-hand ALV and choosing *Add the Same Level*
  - A tree element must be selected and a new item is inserted to the end of the list.
- ☐ Dragging an element from the left-hand ALV to the tree: the result will depend on the tree element onto which the new element is dropped.
  - If the element is dropped onto the logical transaction, it will be inserted to the end of the list.
  - If the element is dropped onto the menu, the dialog box for choosing one of the two options will appear: *Add as Sub Node* or *Add the Same Level*.
- ☐ Selecting an item in the tree and choosing the buttons to change the sequence (up and down)

The user can change the main menu by selecting the *Main* checkbox for a menu element (in the left-hand ALV).

The user can display a submenu in the right-hand tree:

- ☐ By selecting a menu in the left-hand ALV and choosing *Display Menu*
- ☐ By selecting a menu item in the tree and choosing *Next Level* in the tree toolbar. The reverse action is *Previous Level*.

The tool enables the user to manage the menus catalog:

- ☐ To add user-specific menus to the menu catalog (choose *New* in the lefthand ALV)
- ☐ To delete user-specific menus from the menu catalog (choose *Delete* in the left-hand ALV)
- ☐ To change user-specific menu descriptions in the menu catalog (choose *Change* in the left-hand ALV)
- ☐ To manage the RF texts for the menus (choose *Object Texts* in the lefthand ALV)

## 6.2 Screen Manager

You can use the RF screen manager, a tool that enables you to customize the appearance of RF presentation screens, to ensure that the screens are consistent with the attributes of the presentation devices being used.

The RF screen manager enables you to do the following:

- ☐ Create, copy, and delete display profiles
- ☐ Edit the screens of a display profile

Display profile \*\* is provided with the standard SAP system.

### 6.2.1 Create, Copy, and Delete Display Profiles

By defining your own display profiles, you can determine the following screen display characteristics:

- ☐ Screen size
- ☐ Screen element attributes, including:
  - Number of buttons available for the screen
  - Text length for buttons, logical transactions, and menu items
  - How messages are displayed
- ☐ Screen template function groups and screen numbers

You can also create a new display profile based on an existing one and delete an existing display profile. Even if the RFUI is developed for a character-based device, customers can raise a claim to use it in a graphical environment via ITSmobile. In this case, a new display profile must be created. For graphical devices, the following screen dimensions could be feasible:

- ☐ Width: max. 19/20 columns for 240 pixels or 25 columns for 320 pixels
- ☐ Height: max. 12 rows for 320 pixels

Note that these values are experimental. You must check the actual environment on the mobile device to determine whether they are appropriate.

#### 6.2.1.1 Creating a Display Profile

1. Open the *Display Profile* tab page.
2. Enter a two-digit identifier for your display profile and choose *Create*.  
The *Screen Manager* dialog box appears.
3. Enter the following details for the display profile:
  - Text description
  - Screen height and width
  - Screen element attributes
  - Function group and screen number of the screen template.

If you choose to display messages in the status line (that is, you enter *1* in the *Message Display* field), you must also enter a function group and screen number for the secondary screen template containing the status line instead of buttons. If you want to use your own GUI title you must enter the function group name and title number.



If you want to immediately create the sub-screens, proceed as follows:

1. Set the *Create Sub-Screens* indicator.
2. Enter the function group of the sub-screen.
3. If you want the system to use the standard screens and convert them to new screens based on the size parameters of your display profile, select *Convert Screens*.

This option is desirable for the mass creation of screens, especially if you do not intend to make large changes to the screens. If you want the system to copy the standard screens as they are, select *Copy Screens*. If you do not want to create sub-screens immediately, do not set the *Create Sub-Screens* indicator. The display profile created will reference the standard or source sub-screens.

4. Choose *Enter*.

#### 6.2.1.2 Copying a Display Profile

1. Choose the *Display Profile* tab page.
2. Enter the identifier of the display profile that you want to form the basis of a new display profile.
3. Choose *Copy*.

The *Screen Manager* dialog box appears, containing the attributes of the source display profile.

4. Enter the destination display profile identifier and description. You can also change any of the other attributes.
5. Choose *Enter* to copy the display profile.

#### 6.2.1.3 Guideline for Screen Conversion

The screen conversion strategy is based on the height and width of the new screen.

1. First of all the elements are replaced to fit the new number of rows on the screen.
  - If the original screen is taller than the logic tries to merge rows.
  - If the new screen is taller than the logic tries to merge rows.
2. Once the new screen height is reached by either merging or splitting, then the method reconstructs the elements row by row.
  - If the new screen width is shorter than the original then the elements are resized.
  - Texts are replaced with the shortest label available in the dictionary.
  - The minimal length of a field is 1 character.
  - All elements are separated by a space.
3. The step-loops are handled exceptionally:
  - Step-loop rows are not split to multiple lines.
  - The number of rows in the step-loop are reduced if the new screen is smaller.

**Consequence:** If you have too many fields in a row then it's possible that the last elements will not fit to the new screen because of the minimum-size requirements.

#### Example:

One row on the original screen contains the following elements:

- ☐ Start Date (text element), length: 10
- ☐ Start Date (input/output field), length: 10
- ☐ End Date (text element), length: 8
- ☐ End Date (input/output field), length: 10

The total length of the row is 41 (all fields are separated by space). The minimal length of the row is calculated in the following way:

- ☐ The first start date is a text element and the short label can be used instead of the current one ('StDt') which has length: 4.
- ☐ The second start date is an I/O field so the minimum length is 1.
- ☐ The first end date is a text element and the short label can be used instead of the current one ('EnDt') which has length: 4.
- ☐ The second end date is an I/O field so the minimum length is 1.
- ☐ Each field is separated by a space.

The minimal length for this row is 13. If a lower destination screen width is set and the row can't be split – because the new screen is not taller than the original – then not every element of this row will fit to the new

screen.

#### 6.2.1.4 Deleting a Display Profile

1. Choose the *Display Profile* tab page.
2. Enter the display profile identifier and choose *Delete*.  
A query message appears.
3. Confirm that you want to delete the display profile and its corresponding screens.

### 6.2.2 Edit Screens of a Display Profile

After creating a display profile, you can adjust the size and position of screen elements (such as menus and buttons) to fit the physical dimensions of your presentation devices. The RF screen manager enables you to do the following:

- ☐ Analyze screen compression and overlapping of lines and columns before creating new screens
- ☐ Edit and display screen templates
- ☐ Manually create, copy, edit, or display sub-screens
- ☐ Automatically create sub-screens based on conversion analysis results
- ☐ Maintain Customizing settings for sub-screens (mapping of sub-screens to logical transaction steps)

#### 6.2.2.1 Screen Maintenance

1. Choose the *Screens* tab page.
2. Enter one or more selection criteria for the screens that you want to maintain.
3. Choose *Screens*.  
The *Screen Manager* appears.
4. The top ALV contains screen template information for the relevant display profile:
  1. If you want to display a screen template in the *Screen Painter*, choose the line corresponding to the screen template and choose *Display Screen*.
  2. If you want to manually edit a screen template in the *Screen Painter*, choose the line corresponding to the screen template and choose *Edit Screen*.
5. The bottom ALV contains information about all of the relevant sub-screens, including the following:
  - Screen conversion status, which is represented by one of the following three traffic lights:
    - *Green*: The sub-screen exists and matches the display profile settings.
    - *Yellow*: The sub-screen exists but does not match the display profile settings (that is, the sub-screen is not fully adjusted to the sub-screen template area).
    - *Red*: The sub-screen does not yet exist. This is the case if you did not select the *Create Sub-Screens* indicator when you created the display profile (pursuant to the step above).  
Presentation context, including the following:
      - Presentation profile
      - Personalization profile
      - Logical transaction
      - Step
      - State
  - Screen program and number
  - Screen conversion analysis results, namely the lines deficit and columns deficit
6. You can do any of the following from the toolbar of the bottom ALV by choosing the corresponding buttons:
  - Create, copy, change, or delete the sub-screen Customizing settings (mapping of the selected sub-screen to a logical transaction step)
  - Enable/disable the *Skip Shortcut* function for a sub-screen
  - If a sub-screen has not already been created, you can either create it manually in the *Screen Painter* (*Create Screen*) or trigger its automatic creation based on the conversion analysis results (*Convert Screen*).
  - Copy an existing sub-screen (*Copy Screen*). In this case, you must enter the function group and number of the sub-screen template.
  - Edit (*Edit Screen*) or display (*Display Screen*) an existing sub-screen in the *Screen Painter*

## 6.3 Wizards

You launch wizards directly from an active RF transaction by pressing **CTRL+SHIFT+F1**.

### 6.3.1 Split Screen

This wizard guides you through the steps necessary to split the RF transaction screen into several screens. These screens are then displayed in your preferred sequence. You can also configure the function codes that are displayed on each resulting screen.

The wizard contains the following steps:

- ☐ Assign Fields to Split Screens
- ☐ Assign Function Codes to Split Screens / Assignment
- ☐ Assign Function Codes to Split Screens / Pushbuttons
- ☐ Define Target Function Group and Screen Numbers
- ☐ Define Personalization Profile
- ☐ Complete (Creating the new screens and Customizing in the database)

### 6.3.2 Modify Screen

This wizard guides you through the steps necessary to modify an RF transaction screen. Each time you add or remove fields from the screen, the wizard generates an updated screen. To display the new screen to a specific group of users, enter the personalization profile of the users. The wizard then automatically adjusts the Customizing.

Once you run the wizard, the new screen is displayed in Screen Painter so that you can verify the contents or make manual adjustments.

The wizard contains the following steps:

- ☐ Select Target Screen Fields
- ☐ Assign Verification Fields
- ☐ Define Target Function Group and Screen Number
- ☐ Define Personalization Profile
- ☐ Complete (Creating the new screens and Customizing in the database)

### 6.3.3 Error Message Handling in RF Wizard

Since an error message can be thrown in the conversion exit, the RF framework must be able to catch that error message. This will also catch the messages from the RF wizard. As a result, if an error occurs in the RF wizard, the wizard closes and the RF framework displays the error message.

If you work with the RF wizard on your desktop, we recommend setting parameter ID `/SCWM/RF_WIZ_ACT` in your own profile.

To set the parameter ID:

- ☐ Choose *System → User Profile → Own Data*.
- ☐ On the *Parameters* tab page, enter the following data:

Parameter ID: `/SCWM/RF_WIZ_ACT`

Parameter Value: **X**

When this parameter ID is configured, the RF wizard does not close if an error message is issued. Instead, the message is displayed within the wizard.

This parameter ID can be used only in a development or test system, and not in live system since it is not beneficial to launch the RF wizard in a live system.

## 6.4 RF Log

You can log transactions used in the radio frequency (RF) framework to allow you to identify the following situations:

- Error messages, for example, system messages raised by warehouse task confirmation or incorrect validations
- Incorrect validations, for example, the same bin is always validated incorrectly because the bar code label isn't right
- When users use exception codes, for example, a user always uses exception code *Change Destination Bin* to confirm a warehouse task
- How a user uses or navigates within an RF transaction
- The step flow within an RF transaction, for example, is a customer-specific step called
- Customizing changes to the RF framework during runtime using BADIs in enhancement spot `/SCWM/ES_RF_CUST`

The RF log doesn't measure the performance of RF transactions (for more information, see SAP Note [1595305](#)).

You can use *BAdI: Write Radio Frequency Log Entries* (`/SCWM/EX_RF_LOGGING`) to log user actions in the RF framework. The logging is integrated at different places in the RF framework and can be switched on and off from the *SAP Easy Access* screen by choosing *EWM* → *Settings* → *Resource Management* → *Activate Radio Frequency Log* (transaction `/SCWM/RFLOGACT`).

To be independent of the logical unit of work (LUW) of the RF transaction, the log entries are written by using a secondary database connection named `R/3*EWM_2ND_CONNECT_RF_LOG`. With that, we can perform a COMMIT at a different point in time than the main LUW of the RF transaction. For more information, see [Service Connections to the Standard Database](#).

#### 6.4.1 Activation

You activate the RF log on the *SAP Easy Access* screen by choosing *Extended Warehouse Management* → *Settings* → *Resource Management* → *Activate Radio Frequency Log*.

You can switch the RF log on and off based on the following attributes:

- Warehouse
- Queue
- Resource
- User
- Data Entry
- Logical transaction

You can also decide at which level the log entries are saved on the database, that is:

- After each log entry, enhance the runtime of the RF transaction (appr. 13% in synchronous postings and 37% in asynchronous postings of warehouse task confirmation and delivery updates)  
Log entries are also saved if there's a lost connection.
- At new logical transaction steps, enhance runtime of RF transaction (appr. 4 % in synchronous and 18% in asynchronous posting of warehouse task and delivery)  
Log entries might not be saved if there's a lost connection.

#### 6.4.2 Writing of Log Entries

The log entries are added to the RF log using a fallback implementation (`/SCWM/CL_EI_RF_LOGGING`) of *BAdI: Write Radio Frequency Log Entries* (`/SCWM/EX_RF_LOGGING`) in enhancement spot `/SCWM/ES_RF_LOG`, interface `/SCWM/IF_EX_RF_LOGGING`.

The following RF activities are added:

Log Activity	Description
A	RF Logon
B	RF Logoff
C	RF Transaction Start
D	RF Transaction End
E	RF Menu Selection
F	RF Message

G	RF Function Code Trigger
H	RF Validation (Positive and Negative)
I	RF Screen Call
J	RF Step Flow Call
K	RF Exception Trigger
L	RF Field Input
M	RF Customizing Changed by BAdI

Each of the log activities have a corresponding method in the BAdI interface.  
The log entries are stored in table /SCWM/RFLOG.

## 6.4.3 Monitoring

The system displays the RF log entries in the warehouse management monitor under *Resource Management* → *RF Log*.

Selection Screen:

ALV List:

RF Log										Exception Ref	ObjType	Ref. Doc.
Resource	Created On	Created At	Log Activity Desc.	Log Act User	Log Tra.	Log. Trans. Desc.	Step	Step Description	Msg Type	Message		
HLOP2	09.06.2020	08:36:34	798 RF Screen Call	I	RADMANN	PISYSG	System-guided pick	PICPMT	Combined Picking	Screen /SCWM/SAPLRF_PICKING_PM / 0510 called	WT	1000054101
HLOP2	09.06.2020	08:36:39	538 RF Function Code ...	G	RADMANN	PISYSG	System-guided pick	PICPMT	Combined Picking	"Enter" key with assigned function code ENTER chosen		
HLOP2	09.06.2020	08:36:39	544 RF Field Input	L	RADMANN	PISYSG	System-guided pick	PICPMT	Combined Picking	Value 4711 entered in field /SCWM/S_RF_ORDIM_CONFIRM-VLENR_VERIF (Verification Ssce ...		4
HLOP2	09.06.2020	08:36:39	193 RF Validation	H	RADMANN	PISYSG	System-guided pick	PICPMT	Combined Picking	Neg. validation field VLENR_VERIF vs VLENR value 4711 vs 0000000000080000099		
HLOP2	09.06.2020	08:36:39	901 RF Message	F	RADMANN	PISYSG	System-guided pick	PICPMT	Combined Picking	Product PROD-M01 does not exist in handling unit 4711		
HLOP2	09.06.2020	08:36:39	903 RF Validation	H	RADMANN	PISYSG	System-guided pick	PICPMT	Combined Picking	Pos. validation field DLOGPOS_EXT_VLENR_VERIF vs DLOGPOS_EXT_WT value		
HLOP2	09.06.2020	08:36:39	905 RF Validation	H	RADMANN	PISYSG	System-guided pick	PICPMT	Combined Picking	Pos. validation field VLPLA_VERIF vs VLPLA value T010-02-02-B		
HLOP2	09.06.2020	08:36:39	906 RF Screen Call	I	RADMANN	PISYSG	System-guided pick	PICPMT	Combined Picking	Screen /SCWM/SAPLRF_PICKING_PM / 0510 called	WT	1000054101
HLOP2	09.06.2020	08:36:42	225 RF Function Code ...	G	RADMANN	PISYSG	System-guided pick	PICPMT	Combined Picking	Function key F7 (BACKF) chosen		
HLOP2	09.06.2020	08:36:42	232 RF Step Flow Call	J	RADMANN	PISYSG	System-guided pick	PICPMT	Combined Picking	Function module /SCWM/RF_PICK_PICPMT_PA1 of step PICPMT called		

- 1: The creation time is in milliseconds.
- 2: Description fields are determined during monitor data selection and are not stored on the database, for system performance reasons.
- 3: Message texts are determined during monitor data selection. The database only contains the message ID, number, and variables.
- 4: You can access reference documents from the warehouse management monitor .

## 6.4.4 Reference Objects

When adding a log entry, the system determines which reference object to display for the log entry. The system can display only one reference object for each log entry. If there is more than one relevant reference object, the system displays the most important one. For example, if the system determines a warehouse order and a warehouse task, the system displays the warehouse task as the reference object for the log entry. The warehouse task is more specific and you can see the warehouse order details in the warehouse task.

In our fallback class /SCWM/CL\_EI\_RF\_LOGGING in *BAdI: Write Radio Frequency Log Entries*, there are two ways to determine the reference objects:

- By field name: The system analyzes the application data for specific field names, for example, /SCWM/S\_RF\_SELECTION-WHO. The system knows that this field contains a warehouse order. This method is used for log activity RF Field Input.
- By data container: The system analyzes the data containers used in the RF transaction. Normally they are set by the developer at the beginning of the RF transaction using method /SCWM/CL\_RF\_BLL\_SRVC=>SET\_SCREEN\_PARAM. The system searches the data container for certain

domains, for example, `/SCWM/DO_HUIDENT`. In this case, we know that the field contains a handling unit (HU). This method is used for log activity RF Screen Call and RF Exception Trigger. This doesn't find all reference objects.

The warehouse management monitor uses hotspot service `CUSTOM` for navigation from reference objects. Fallback implementation (`/SCWM/CL_EI_MONITOR_HOTSPOT`) in *BAdI: Custom Implementation of a Monitor Hotspot* (`/SCWM/EX_MONITOR_HOTSPOT`) in enhancement spot `/SCWM/ES_MONITOR_FRAMEWORK` navigates from the reference object to the corresponding transaction.

The supported reference objects are as follows:

- From a warehouse task to the *Display Warehouse Task* transaction
- From a warehouse order to the *Confirm Warehouse Task* transaction
- From a physical inventory counting document to the *Physical Inventory Document - Process* transaction
- From a HU to the *Packing* transaction
- From an inbound delivery order to the *Maintain Inbound Delivery* transaction
- From an outbound delivery order to the *Maintain Outbound Delivery Order* transaction

Based on the BAdI concept, you can also introduce your own reference objects.

#### 6.4.5 Deletion of Log Entries

You can delete RF log entries using report *Delete Entries in RF Log* (`/SCWM/R_RF_LOG_DELETE`) or on the *SAP Easy Access* screen by choosing *Extended Warehouse Management* → *Settings* → *Resource Management* → *Delete Radio Frequency Log* (transaction `/SCWM/RF_DEL_LOG`).

We recommend deleting log entries based on how often you use the RF log. It may be sufficient to delete the log entries manually on a regular basis. If you run the RF log permanently, we recommend scheduling a background job to delete the data on a regular basis based on the retention time.

## 7 SAP GUI for HTML


We've enhanced SAP GUI for HTML with features specifically for the radio frequency (RF) framework. The functionality in the back end is the same as in ITSmobile (see [ITSmobile](#)) as it is the RF framework and the existing RF transactions. The functionality in the front end is the same as SAP GUI for HTML with some optimization for using on mobile devices, for example, hiding the header and footer line to allow more space for the RF screen.

Unlike with ITSmobile, the system doesn't need to generate HTML templates from the ABAP dynpros. The screens are generated directly from the ABAP dynpros. This ensures you always use the latest screen version. With ITSmobile, you have to regenerate the HTML files if there are changes to the generator.

But without the generator and the HTML files when using ITSmobile, you can't change a RF screen (such as CSS file or Visual Editor). For SAP GUI for HTML, you must use SAP Screen Personas for this (for more information, see [SAP Screen Personas](#) and how-to guide *SAP Screen Personas for Mobile RF Devices in Extended Warehouse Management in SAP S/4HANA* on the [SAP Community](#)). SAP Screen Personas is a tool to adjust screens to customer needs. This tool offers a WYSIWYG editor and a script engine for a huge range of adoption. SAP Screen Personas is started by using a SICF service.

For ITSmobile, the service is named `RFUI`. For SAP GUI for HTML, the service is named `EWM_MOBGUI`.

## RF Architecture



For more information about SAP GUI for HTML and Extended Warehouse Management, see SAP Note [3048632](#) (contains limitations and additional info).

Responsiveness of RF screens is still not supported, which causes the following issues:

- The system doesn't automatically adjust RF screens to the screen size of the RF device.
- If you have two RF devices using portrait mode with different resolutions, you must adjust the screens by zooming in and out as needed.
- If you have two RF devices using portrait and landscape mode, you must use the different display profiles that are linked to two different screens.  
If you want to develop your own RF screens, you need to create two dynpros (one for landscape mode and one for portrait mode).

### 7.1 Design Mode

You can't change RF screens running on SAP GUI for HTML in the same way as those running on ITSmobile (for example, own CSS file, Visual Editor, or own HTML generator). You can change RF screens running on SAP GUI for HTML only by using SAP Screen Personas.

SAP Screen Personas can only be triggered directly while using the RF screens. You can't to make the changes directly from the ABAP Dynpro Screen Painter (SE51).

SAP Screen Personas allows you to adjust only screen elements that are displayed on a screen when the screen is being used. If some of the elements or screens are not displayed based on context (for example, serial numbers), you can't adjust these elements. Consequently, if you want to influence serial number fields, you have to work with a serialized product.

Example: Screen 501 from /SCWM/RF\_PICKING\_PM

Actual RF Screen	ABAP Dynpro (as seen in SE51)	Design mode with all fields and function codes
------------------	-------------------------------	--



To overcome this limitation, you can use design mode. You can access design mode from any screen in an RF transaction and the screen is the basis for the RF screen changes by SAP Screen Personas.

With design mode, you can see all the screens of a RF transaction, including all possible fields that belong to the RF transaction. You can move through all function codes without needing to prepare the necessary data upfront. This makes it much easier to adopt the RF screens for an RF transaction using SAP Screen Personas.

Screen navigation during design mode:

Trigger Design Mode	Ctrl+Shift+F2
Next Screen	Ctrl+Shift+F3
Previous Screen	Ctrl+Shift+F4
End Design Mode	Restart RFUI

During design mode, the RF framework reads the corresponding Customizing entries and works on this data. You can change all the screens that belong to the started RF transaction. The screens are sorted according to the screen number (there is no logical order like in the RF transaction).

## Note

- If you use landscape mode and portrait mode screens in your warehouse, make sure that you use the right display profile before you access design mode. Otherwise you'll have to make the changes twice because the Customizing entries are read with the display profile of the presentation device that you entered at RF logon.
- You don't have to make the changes for each different RF transaction of the same process (for example, Picking System-Guided, Picking by WO, or Picking by HU). Only the selection screen of these RF transactions are different but they then have screens in common. You only need to change common screens in the same process once.
- For better orientation, the title bar is changed in design mode. In SAP S/4HANA, you see the technical keys of the dynpro, for example, PIBWHO PIMTTO /SCWM/SAPLRF\_PICKING\_PM 0501.
- You can't access design mode in a productive system.

[www.sap.com/contactsap](http://www.sap.com/contactsap)

© 2022 SAP SE or an SAP affiliate company. All rights reserved.

No part of this publication may be reproduced or transmitted in any form or for any purpose without the express permission of SAP SE or an SAP affiliate company.

The information contained herein may be changed without prior notice. Some software products marketed by SAP SE and its distributors contain proprietary software components of other software vendors. National product specifications may vary.

These materials are provided by SAP SE or an SAP affiliate company for informational purposes only, without representation or warranty of any kind, and SAP or its affiliated companies shall not be liable for errors or omissions with respect to the materials. The only warranties for SAP or SAP affiliate company products and services are those that are set forth in the express warranty statements accompanying such products and services, if any. Nothing herein should be construed as constituting an additional warranty.

In particular, SAP SE or its affiliated companies have no obligation to pursue any course of business outlined in this document or any related presentation, or to develop or release any functionality mentioned therein. This document, or any related presentation, and SAP SE's or its affiliated companies' strategy and possible future developments, products, and/or platform directions and functionality are all subject to change and may be changed by SAP SE or its affiliated companies at any time for any reason without notice. The information in this document is not a commitment, promise, or legal obligation to deliver any material, code, or functionality. All forward-looking statements are subject to various risks and uncertainties that could cause actual results to differ materially from expectations. Readers are cautioned not to place undue reliance on these forward-looking statements, and they should not be relied upon in making purchasing decisions.

SAP and other SAP products and services mentioned herein as well as their respective logos are trademarks or registered trademarks of SAP SE (or an SAP affiliate company) in Germany and other

